FlyCapture2 C 2.13.3.61

Generated by Doxygen 1.7.5

Wed Apr 3 2019 19:08:25

#### **Contents**

1	Software Licensing Information 1							
2	Deprecated List 3							
3	Mod	ule Inde	ЭХ	Ę	5			
	3.1	Module	es		5			
4	Data	Structi	ure Index	7	7			
	4.1	Data S	tructures		7			
5	File	Index		11	1			
	5.1	File Lis	st		1			
6	Mod	ule Doc	umentatio	on 13	3			
	6.1	Bus Ma	anager Op	eration	3			
		6.1.1	Detailed	Description	5			
		6.1.2	Function	Documentation	5			
			6.1.2.1	fc2DiscoverGigECameras	5			
			6.1.2.2	fc2FireBusReset	5			
			6.1.2.3	fc2ForceAllIPAddressesAutomatically 16	3			
			6.1.2.4	fc2ForceIPAddressAutomatically	3			
			6.1.2.5	fc2ForceIPAddressToCamera	3			
			6.1.2.6	fc2GetCameraFromIndex	7			
			6.1.2.7	fc2GetCameraFromIPAddress	7			
			6.1.2.8	fc2GetCameraFromSerialNumber	7			
			6.1.2.9	fc2GetCameraSerialNumberFromIndex	3			
			6.1.2.10	fc2GetDeviceFromIndex	3			

ii CONTENTS

		6.1.2.11	fc2GetInterfaceTypeFromGuid
		6.1.2.12	fc2GetNumOfCameras
		6.1.2.13	fc2GetNumOfDevices
		6.1.2.14	fc2GetTopology
		6.1.2.15	fc2GetUsbLinkInfo
		6.1.2.16	fc2GetUsbPortStatus 20
		6.1.2.17	fc2lsCameraControlable
		6.1.2.18	fc2ReadPhyRegister
		6.1.2.19	fc2RegisterCallback
		6.1.2.20	fc2RescanBus
		6.1.2.21	fc2UnregisterCallback
		6.1.2.22	fc2WritePhyRegister
6.2	Conne	ction and I	mage Retrieval
	6.2.1	Detailed	Description
	6.2.2	Function	Documentation
		6.2.2.1	fc2Connect
		6.2.2.2	fc2Disconnect
		6.2.2.3	fc2GetConfiguration
		6.2.2.4	fc2lsConnected
		6.2.2.5	fc2RetrieveBuffer
		6.2.2.6	fc2SetCallback
		6.2.2.7	fc2SetConfiguration
		6.2.2.8	fc2SetUserBuffers
		6.2.2.9	fc2StartCapture
		6.2.2.10	fc2StartCaptureCallback 29
		6.2.2.11	fc2StartSyncCapture
		6.2.2.12	fc2StartSyncCaptureCallback
		6.2.2.13	fc2StopCapture
		6.2.2.14	fc2WaitForBufferEvent
6.3	Informa	ation and F	Properties
	6.3.1	Detailed	Description
	6.3.2	Function	Documentation
		6.3.2.1	fc2GetCameraInfo
		6.3.2.2	fc2GetProperty

CONTENTS iii

		6.3.2.3	fc2GetPropertyInfo
		6.3.2.4	fc2SetProperty
		6.3.2.5	fc2SetPropertyBroadcast
6.4	Genera	al Purpose	Input / Output
	6.4.1	Detailed	Description
	6.4.2	Function	Documentation
		6.4.2.1	fc2GetGPIOPinDirection
		6.4.2.2	fc2SetGPIOPinDirection
		6.4.2.3	fc2SetGPIOPinDirectionBroadcast
6.5	Trigger	·	
	6.5.1	Detailed	Description
	6.5.2	Function	Documentation
		6.5.2.1	fc2FireSoftwareTrigger
		6.5.2.2	fc2FireSoftwareTriggerBroadcast
		6.5.2.3	fc2GetTriggerDelay
		6.5.2.4	fc2GetTriggerDelayInfo
		6.5.2.5	fc2GetTriggerMode
		6.5.2.6	fc2GetTriggerModeInfo
		6.5.2.7	fc2SetTriggerDelay
		6.5.2.8	fc2SetTriggerDelayBroadcast 41
		6.5.2.9	fc2SetTriggerMode
		6.5.2.10	fc2SetTriggerModeBroadcast
6.6	Strobe		
	6.6.1	Detailed	Description
	6.6.2	Function	Documentation
		6.6.2.1	fc2GetStrobe
		6.6.2.2	fc2GetStrobeInfo
		6.6.2.3	fc2SetStrobe
		6.6.2.4	fc2SetStrobeBroadcast
6.7	Look U	Ip Table .	
	6.7.1	Detailed	Description
	6.7.2	Function	Documentation
		6.7.2.1	fc2EnableLUT
		6.7.2.2	fc2GetActiveLUTBank

iv CONTENTS

		6.7.2.3	fc2GetLUTBankInfo	47
		6.7.2.4	fc2GetLUTChannel	47
		6.7.2.5	fc2GetLUTInfo	48
		6.7.2.6	fc2SetActiveLUTBank	48
		6.7.2.7	fc2SetLUTChannel	49
6.8	Memor	y Channel	s	50
	6.8.1	Detailed	Description	50
	6.8.2	Function	Documentation	50
		6.8.2.1	fc2GetEmbeddedImageInfo	50
		6.8.2.2	fc2GetMemoryChannel	51
		6.8.2.3	fc2GetMemoryChannelInfo	51
		6.8.2.4	fc2RestoreFromMemoryChannel	52
		6.8.2.5	fc2SaveToMemoryChannel	52
		6.8.2.6	fc2SetEmbeddedImageInfo	52
6.9	Registe	er Operatio	on	54
	6.9.1	Detailed	Description	54
	6.9.2	Function	Documentation	54
		6.9.2.1	fc2GetRegisterString	54
		6.9.2.2	fc2ReadRegister	55
		6.9.2.3	fc2ReadRegisterBlock	55
		6.9.2.4	fc2WriteRegister	55
		6.9.2.5	fc2WriteRegisterBlock	56
		6.9.2.6	fc2WriteRegisterBroadcast	56
6.10	DCAM	Formats		58
	6.10.1	Detailed	Description	58
	6.10.2	Function	Documentation	58
		6.10.2.1	fc2GetVideoModeAndFrameRate	58
		6.10.2.2	fc2GetVideoModeAndFrameRateInfo	59
		6.10.2.3	fc2SetVideoModeAndFrameRate	59
6.11	Format	7		60
	6.11.1	Detailed	Description	60
	6.11.2	Function	Documentation	60
		6.11.2.1	fc2GetFormat7Configuration	60
		6.11.2.2	fc2GetFormat7Info	61

CONTENTS

	6.11.2.3	fc2SetFormat7Configuration	61
	6.11.2.4	fc2SetFormat7ConfigurationPacket	61
	6.11.2.5	fc2ValidateFormat7Settings	62
6.12 GVCP	Register C	Operation	63
6.12.1	Detailed	Description	63
6.12.2	Function	Documentation	63
	6.12.2.1	fc2ReadGVCPMemory	63
	6.12.2.2	fc2ReadGVCPRegister	64
	6.12.2.3	fc2ReadGVCPRegisterBlock	64
	6.12.2.4	fc2WriteGVCPMemory	64
	6.12.2.5	fc2WriteGVCPRegister	65
	6.12.2.6	fc2WriteGVCPRegisterBlock	65
	6.12.2.7	fc2WriteGVCPRegisterBroadcast	65
6.13 GigE p	roperty ma	anipulation	67
6.13.1	Detailed	Description	67
6.13.2	Function	Documentation	67
	6.13.2.1	fc2DiscoverGigEPacketSize	67
	6.13.2.2	fc2GetGigEProperty	67
	6.13.2.3	fc2SetGigEProperty	68
6.14 GigE in	mage settii	ngs	69
6.14.1	Detailed	Description	69
6.14.2	Function	Documentation	69
	6.14.2.1	fc2GetGigEImageSettings	69
	6.14.2.2	fc2GetGigEImageSettingsInfo	70
	6.14.2.3	fc2GetGigEImagingMode	70
	6.14.2.4	fc2QueryGigEImagingMode	70
	6.14.2.5	fc2SetGigEImageSettings	71
	6.14.2.6	fc2SetGigEImagingMode	71
6.15 GigE in	mage binni	ing settings	72
6.15.1	Detailed	Description	72
6.15.2	Function	Documentation	72
	6.15.2.1	fc2GetGigEImageBinningSettings	72
	6.15.2.2	fc2SetGigEImageBinningSettings	72
6.16 GigE in	mage strea	nm configuration	74

vi CONTENTS

0404	Detailed Description 74					
6.16.1		Detailed Description				
6.16.2		Documentation				
	6.16.2.1	fc2GetGigEConfig				
		fc2GetGigEStreamChannelInfo				
		fc2GetNumStreamChannels				
		fc2SetGigEConfig				
		fc2SetGigEStreamChannelInfo				
6.17 Image	Operation		77			
6.17.1	Detailed I	Description	78			
6.17.2	Function	Documentation	78			
	6.17.2.1	fc2CalculateImageStatistics	78			
	6.17.2.2	fc2ConvertImage	79			
	6.17.2.3	fc2ConvertImageTo	79			
	6.17.2.4	fc2CreateImage	79			
	6.17.2.5	fc2DestroyImage	80			
	6.17.2.6	fc2DetermineBitsPerPixel	80			
	6.17.2.7	fc2GetDefaultColorProcessing	80			
	6.17.2.8	fc2GetDefaultOutputFormat	81			
	6.17.2.9	fc2GetImageColorProcessing	81			
	6.17.2.10	fc2GetImageData	81			
	6.17.2.11	fc2GetImageDimensions	82			
	6.17.2.12	fc2GetImageMetadata	82			
	6.17.2.13	fc2GetImageTimeStamp	82			
	6.17.2.14	fc2SaveImage	83			
	6.17.2.15	fc2SaveImageWithOption	83			
	6.17.2.16	fc2SetDefaultColorProcessing	83			
	6.17.2.17	fc2SetDefaultOutputFormat	84			
	6.17.2.18	fc2SetImageColorProcessing	84			
	6.17.2.19	fc2SetImageData	85			
	6.17.2.20	fc2SetImageDimensions	85			
6.18 Image	Statistics C	Operation	86			
		· Description				
		Documentation				
		fc2CreateImageStatistics	87			

CONTENTS vii

		6.18.2.2	fc2DestroyImageStatistics	37
		6.18.2.3	fc2GetChannelHistogram	8
		6.18.2.4	fc2GetChannelMean	88
		6.18.2.5	fc2GetChannelNumPixelValues	88
		6.18.2.6	fc2GetChannelPixelValueRange	39
		6.18.2.7	fc2GetChannelRange	19
		6.18.2.8	fc2GetChannelStatus	90
		6.18.2.9	fc2GetImageStatistics	90
		6.18.2.10	fc2ImageStatisticsDisableAll	1
		6.18.2.11	fc2ImageStatisticsEnableAll	1
		6.18.2.12	fc2ImageStatisticsEnableGreyOnly 9	2
		6.18.2.13	fc2ImageStatisticsEnableHSLOnly 9	2
		6.18.2.14	fc2ImageStatisticsEnableRGBOnly 9	12
		6.18.2.15	fc2SetChannelStatus	13
6.19	Topolog	yNode Op	eration	14
	6.19.1	Detailed D	Description	95
	6.19.2	Function I	Documentation	95
		6.19.2.1	fc2CreateTopologyNode	15
		6.19.2.2	fc2DestroyTopologyNode	15
		6.19.2.3	fc2TopologyNodeAddChild	16
		6.19.2.4	fc2TopologyNodeAddPortType	96
		6.19.2.5	fc2TopologyNodeAssignGuidToNode 9	16
		6.19.2.6	fc2TopologyNodeAssignGuidToNodeEx 9	7
		6.19.2.7	fc2TopologyNodeGetChild	7
		6.19.2.8	fc2TopologyNodeGetDeviceId	8
		6.19.2.9	fc2TopologyNodeGetGuid	8
		6.19.2.10	fc2TopologyNodeGetInterfaceType 9	8
		6.19.2.11	fc2TopologyNodeGetNodeType	9
		6.19.2.12	fc2TopologyNodeGetNumChildren	19
		6.19.2.13	fc2TopologyNodeGetNumPorts	)0
		6.19.2.14	fc2TopologyNodeGetPortType	)0
6.20	Utilities			)1
	6.20.1	Detailed D	Description	)1
	6.20.2	Function I	Documentation	)1

viii CONTENTS

		6.20.2.1	fc2CheckDriver
		6.20.2.2	fc2ErrorToDescription
		6.20.2.3	fc2GetDriverDeviceName
		6.20.2.4	fc2GetLibraryVersion
		6.20.2.5	fc2GetSystemInfo
		6.20.2.6	fc2LaunchBrowser
		6.20.2.7	fc2LaunchCommand
		6.20.2.8	fc2LaunchCommandAsync
		6.20.2.9	fc2LaunchHelp
6.21	TypeDe	efs	
	6.21.1	Define Do	ocumentation
		6.21.1.1	FALSE
		6.21.1.2	FULL_32BIT_VALUE
		6.21.1.3	MAX_STRING_LENGTH
		6.21.1.4	TRUE
	6.21.2	Typedef [	Documentation
		6.21.2.1	BOOL
		6.21.2.2	fc2Context
		6.21.2.3	fc2GuiContext
		6.21.2.4	fc2ImageImpl
		6.21.2.5	fc2ImageStatisticsContext
		6.21.2.6	fc2TopologyNodeContext
		6.21.2.7	fc2VideoContext
6.22	Enume	rations .	
	6.22.1	Enumera	tion Type Documentation
		6.22.1.1	fc2BandwidthAllocation
		6.22.1.2	fc2BayerTileFormat
		6.22.1.3	fc2BusCallbackType
		6.22.1.4	fc2BusSpeed
		6.22.1.5	fc2ColorProcessingAlgorithm
		6.22.1.6	fc2DriverType
		6.22.1.7	fc2Error
		6.22.1.8	fc2FrameRate
		6.22.1.9	fc2GrabMode

CONTENTS ix

		6.22.1.10 fc2GrabTimeout
		6.22.1.11 fc2ImageFileFormat
		6.22.1.12 fc2InterfaceType
		6.22.1.13 fc2Mode
		6.22.1.14 fc2PCleBusSpeed
		6.22.1.15 fc2PixelFormat
		6.22.1.16 fc2PropertyType
		6.22.1.17 fc2VideoMode
6.23	GigE s	pecific enumerations
	6.23.1	Detailed Description
	6.23.2	Enumeration Type Documentation
		6.23.2.1 fc2GigEPropertyType
6.24	Structu	res
6.25	GigE s	pecific structures
	6.25.1	Detailed Description
6.26	IIDC sp	ecific structures
	6.26.1	Detailed Description
6.27	Image	saving structures
	6.27.1	Detailed Description
	6.27.2	Typedef Documentation
		6.27.2.1 fc2AsyncCommandCallback
		6.27.2.2 fc2BusEventCallback
		6.27.2.3 fc2CallbackHandle
		6.27.2.4 fc2CameraEventCallback
		6.27.2.5 fc2ImageEventCallback
	6.27.3	Enumeration Type Documentation
		6.27.3.1 fc2TIFFCompressionMethod
6.28	Video F	Recording Operation
	6.28.1	Detailed Description
	6.28.2	Function Documentation
		6.28.2.1 fc2VideoAppend
		6.28.2.2 fc2VideoAVIOpen
		6.28.2.3 fc2VideoClose
		6.28.2.4 fc2VideoCreate

x CONTENTS

			6.28.2.5	fc2VideoDestroy
			6.28.2.6	fc2VideoH264Open
			6.28.2.7	fc2VideoMJPGOpen
			6.28.2.8	fc2VideoSetMaximumSize
	6.29	Video s	saving stru	ctures
		6.29.1	Detailed	Description
7	Data	Structi	ıre Docun	nentation 133
•	7.1			uct Reference
	7.1	7.1.1	•	Description
		7.1.2		pumentation
		7.1.2	7.1.2.1	frameRate
			7.1.2.2	reserved
	7.2	fc2BMI		ruct Reference
		7.2.1	•	Description
		7.2.2		numentation
			7.2.2.1	indexedColor 8bit
			7.2.2.2	reserved
	7.3	fc2Can	neraInfo St	ruct Reference
		7.3.1		Description
		7.3.2	Field Doo	rumentation
			7.3.2.1	applicationIPAddress
			7.3.2.2	applicationPort
			7.3.2.3	bayerTileFormat
			7.3.2.4	busNumber
			7.3.2.5	ccpStatus
			7.3.2.6	configROM
			7.3.2.7	defaultGateway
			7.3.2.8	driverName
			7.3.2.9	driverType
			7.3.2.10	firmwareBuildTime
			7.3.2.11	firmwareVersion
			7.3.2.12	gigEMajorVersion
			7.3.2.13	gigEMinorVersion

CONTENTS xi

		7.3.2.14	iidcVer
		7.3.2.15	interfaceType
		7.3.2.16	ipAddress
		7.3.2.17	isColorCamera
		7.3.2.18	macAddress
		7.3.2.19	maximumBusSpeed
		7.3.2.20	modelName
		7.3.2.21	nodeNumber
		7.3.2.22	pcieBusSpeed
		7.3.2.23	reserved
		7.3.2.24	sensorInfo
		7.3.2.25	sensorResolution
		7.3.2.26	serialNumber
		7.3.2.27	subnetMask
		7.3.2.28	userDefinedName
		7.3.2.29	vendorName
		7.3.2.30	xmlURL1
		7.3.2.31	xmlURL2
7.4	fc2Car	neraStats	Struct Reference
	7.4.1	Detailed	Description
	7.4.2	Field Doo	cumentation
		7.4.2.1	cameraCurrents
		7.4.2.2	cameraPowerUp
		7.4.2.3	cameraVoltages
		7.4.2.4	imageCorrupt
		7.4.2.5	imageDriverDropped
		7.4.2.6	imageDropped
		7.4.2.7	imageXmitFailed
		7.4.2.8	numCurrents
		7.4.2.9	numResendPacketsReceived
		7.4.2.10	numResendPacketsRequested
		7.4.2.11	numVoltages
		7.4.2.12	portErrors
		7.4.2.13	regReadFailed

xii CONTENTS

		7.4.2.14	regWriteFailed
		7.4.2.15	reserved
		7.4.2.16	temperature
		7.4.2.17	timeSinceBusReset
		7.4.2.18	timeSinceInitialization
		7.4.2.19	timeStamp
7.5	fc2Con	ifig Struct I	Reference
	7.5.1	Detailed	Description
	7.5.2	Field Doo	cumentation
		7.5.2.1	asyncBusSpeed
		7.5.2.2	bandwidthAllocation
		7.5.2.3	grabMode
		7.5.2.4	grabTimeout
		7.5.2.5	highPerformanceRetrieveBuffer
		7.5.2.6	isochBusSpeed144
		7.5.2.7	minNumImageNotifications
		7.5.2.8	numBuffers
		7.5.2.9	numImageNotifications
		7.5.2.10	registerTimeout
		7.5.2.11	registerTimeoutRetries
		7.5.2.12	reserved
7.6	fc2Con	figROM St	truct Reference
	7.6.1	Detailed	Description
	7.6.2	Field Doo	cumentation
		7.6.2.1	chipIdHi
		7.6.2.2	chipIdLo
		7.6.2.3	nodeVendorId
		7.6.2.4	pszKeyword
		7.6.2.5	reserved
		7.6.2.6	unitSpecId
		7.6.2.7	unitSubSWVer
		7.6.2.8	unitSWVer
		7.6.2.9	vendorUniqueInfo_0
		7.6.2.10	vendorUniqueInfo 1

CONTENTS xiii

		7.6.2.11	vendorUniqueInfo_2
		7.6.2.12	vendorUniqueInfo_3
7.7	fc2Emb	oeddedIma	geInfo Struct Reference
	7.7.1	Detailed I	Description
	7.7.2	Field Doo	cumentation
		7.7.2.1	brightness
		7.7.2.2	exposure
		7.7.2.3	frameCounter
		7.7.2.4	gain
		7.7.2.5	GPIOPinState
		7.7.2.6	ROIPosition
		7.7.2.7	shutter
		7.7.2.8	strobePattern
		7.7.2.9	timestamp
		7.7.2.10	whiteBalance
7.8	fc2Emb	oeddedIma	ageInfoProperty Struct Reference
	7.8.1	Detailed I	Description
	7.8.2	Field Doo	cumentation
		7.8.2.1	available
		7.8.2.2	onOff
7.9	fc2Eve	ntCallback	Data Struct Reference
	7.9.1	Field Doo	cumentation
		7.9.1.1	EventData
		7.9.1.2	EventDataSize
		7.9.1.3	EventID
		7.9.1.4	EventName
		7.9.1.5	EventTimestamp
		7.9.1.6	EventUserData
		7.9.1.7	EventUserDataSize
7.10	fc2Eve	ntOptions	Struct Reference
	7.10.1	Detailed I	Description
	7.10.2	Field Doo	cumentation
		7.10.2.1	EventCallbackFcn
		7.10.2.2	EventName

xiv CONTENTS

	7.10.2.3	EventUserData
	7.10.2.4	EventUserDataSize
7.11 fc2For	mat7lmage	Settings Struct Reference
7.11.1	Detailed I	Description
7.11.2	Field Doo	eumentation
	7.11.2.1	height
	7.11.2.2	mode
	7.11.2.3	offsetX
	7.11.2.4	offsetY
	7.11.2.5	pixelFormat
	7.11.2.6	reserved
	7.11.2.7	width
7.12 fc2For	mat7Info S	truct Reference
7.12.1	Detailed I	Description
7.12.2	Field Doo	eumentation
	7.12.2.1	imageHStepSize
	7.12.2.2	imageVStepSize
	7.12.2.3	maxHeight
	7.12.2.4	maxPacketSize
	7.12.2.5	maxWidth
	7.12.2.6	minPacketSize
	7.12.2.7	mode
	7.12.2.8	offsetHStepSize
	7.12.2.9	offsetVStepSize
	7.12.2.10	packetSize
	7.12.2.11	percentage
	7.12.2.12	pixelFormatBitField
	7.12.2.13	reserved
	7.12.2.14	vendorPixelFormatBitField
7.13 fc2For	mat7Packe	tInfo Struct Reference
7.13.1	Detailed I	Description
7.13.2	Field Doo	eumentation
	7.13.2.1	maxBytesPerPacket
	7.13.2.2	recommendedBytesPerPacket

CONTENTS xv

	7.13.2.3	reserved
	7.13.2.4	unitBytesPerPacket
7.14 fc2Gig	EConfig Str	ruct Reference
7.14.1	Detailed [	Description
7.14.2	Field Doc	umentation
	7.14.2.1	enablePacketResend
	7.14.2.2	registerTimeout
	7.14.2.3	registerTimeoutRetries
	7.14.2.4	reserved
7.15 fc2Gig	ElmageSet	tings Struct Reference
7.15.1	Detailed [	Description
7.15.2	Field Doc	umentation
	7.15.2.1	height
	7.15.2.2	offsetX
	7.15.2.3	offsetY
	7.15.2.4	pixelFormat
	7.15.2.5	reserved
	7.15.2.6	width
7.16 fc2Gig	ElmageSet	tingsInfo Struct Reference
7.16.1	Detailed [	Description
7.16.2	Field Doc	umentation
	7.16.2.1	imageHStepSize
	7.16.2.2	imageVStepSize
	7.16.2.3	maxHeight
	7.16.2.4	maxWidth
	7.16.2.5	offsetHStepSize
	7.16.2.6	offsetVStepSize
	7.16.2.7	pixelFormatBitField
	7.16.2.8	reserved
	7.16.2.9	vendorPixelFormatBitField
7.17 fc2Gig	EProperty :	Struct Reference
7.17.1	Detailed [	Description
7.17.2	Field Doc	umentation
	7.17.2.1	isReadable

xvi CONTENTS

	7.17.2.2	isWritable
	7.17.2.3	max
	7.17.2.4	min
	7.17.2.5	propType
	7.17.2.6	reserved
	7.17.2.7	value
7.18 fc2Gig	EStreamC	hannel Struct Reference
7.18.1		Description
7.18.2	Field Doo	cumentation
	7.18.2.1	destinationIpAddress
	7.18.2.2	doNotFragment
	7.18.2.3	hostPort
	7.18.2.4	interPacketDelay
	7.18.2.5	networkInterfaceIndex
	7.18.2.6	packetSize
	7.18.2.7	reserved
	7.18.2.8	sourcePort
7.19 fc2H26	64Option S	truct Reference
7.19.1	Detailed	Description
7.19.2	Field Doo	cumentation
	7.19.2.1	bitrate
	7.19.2.2	frameRate
	7.19.2.3	height
	7.19.2.4	reserved
	7.19.2.5	width
7.20 fc2lma	ige Struct I	Reference
7.20.1	Field Doo	cumentation
	7.20.1.1	bayerFormat
	7.20.1.2	cols
	7.20.1.3	dataSize
	7.20.1.4	format
	7.20.1.5	imageImpl
	7.20.1.6	pData
	7.20.1.7	receivedDataSize

CONTENTS xvii

	7.20.1.8 rows	
	7.20.1.9 stride	
7.21 fc2ImageMetadata Struct Reference		
7.21.1	Detailed Description	
7.21.2	Field Documentation	
	7.21.2.1 embeddedBrightness	
	7.21.2.2 embeddedExposure	
	7.21.2.3 embeddedFrameCounter	
	7.21.2.4 embeddedGain	
	7.21.2.5 embeddedGPIOPinState	
	7.21.2.6 embeddedROIPosition	
	7.21.2.7 embeddedShutter	
	7.21.2.8 embeddedStrobePattern	
	7.21.2.9 embeddedTimeStamp	
	7.21.2.10 embeddedWhiteBalance	
	7.21.2.11 reserved	
7.22 fc2Inte	ernalContext Struct Reference	
7.22.1	Field Documentation	
	7.22.1.1 pBusMgr	
	7.22.1.2 pCamera	
7.23 fc2Inte	ernalGuiContext Struct Reference	
7.23.1	Field Documentation	
	7.23.1.1 pCameraControlDlg	
	7.23.1.2 pCameraSelectionDlg	
7.24 fc2Inte	ernallmageCallback Struct Reference	
7.24.1	Field Documentation	
	7.24.1.1 pCallback	
	7.24.1.2 pCallbackData	
7.25 fc2IPA	ddress Struct Reference	
7.25.1	Detailed Description	
7.25.2	Field Documentation	
	7.25.2.1 octets	
7.26 fc2JPE	EGOption Struct Reference	
7.26.1	Detailed Description	

xviii CONTENTS

7.26.	2 Field Documentation
	7.26.2.1 progressive
	7.26.2.2 quality
	7.26.2.3 reserved
7.27 fc2JF	G2Option Struct Reference
7.27.	1 Detailed Description
7.27.	2 Field Documentation
	7.27.2.1 quality
	7.27.2.2 reserved
7.28 fc2LU	JTData Struct Reference
7.28.	1 Detailed Description
7.28.	2 Field Documentation
	7.28.2.1 enabled
	7.28.2.2 inputBitDepth
	7.28.2.3 numBanks
	7.28.2.4 numChannels
	7.28.2.5 numEntries
	7.28.2.6 outputBitDepth
	7.28.2.7 reserved
	7.28.2.8 supported
7.29 fc2M	ACAddress Struct Reference
7.29.	1 Detailed Description
7.29.	2 Field Documentation
	7.29.2.1 octets
7.30 fc2M	JPGOption Struct Reference
7.30.	1 Detailed Description
7.30.	2 Field Documentation
	7.30.2.1 frameRate
	7.30.2.2 quality
	7.30.2.3 reserved
7.31 fc2P0	GMOption Struct Reference
7.31.	1 Detailed Description
7.31.	2 Field Documentation
	7.31.2.1 binaryFile

CONTENTS xix

	7.31.2.2 reserved
7.32 fc2PG	RGuid Struct Reference
7.32.1	Detailed Description
7.32.2	Field Documentation
	7.32.2.1 value
7.33 fc2PN	GOption Struct Reference
7.33.1	Detailed Description
7.33.2	Field Documentation
	7.33.2.1 compressionLevel
	7.33.2.2 interlaced
	7.33.2.3 reserved
7.34 fc2PP	MOption Struct Reference
7.34.1	Detailed Description
7.34.2	Field Documentation
	7.34.2.1 binaryFile
	7.34.2.2 reserved
7.35 fc2Str	obeControl Struct Reference
7.35.1	Detailed Description
7.35.2	Field Documentation
	7.35.2.1 delay
	7.35.2.2 duration
	7.35.2.3 onOff
	7.35.2.4 polarity
	7.35.2.5 reserved
	7.35.2.6 source
7.36 fc2Str	obeInfo Struct Reference
7.36.1	Detailed Description
7.36.2	Field Documentation
	7.36.2.1 maxValue
	7.36.2.2 minValue
	7.36.2.3 onOffSupported
	7.36.2.4 polaritySupported
	7.36.2.5 present
	7.36.2.6 readOutSupported

XX CONTENTS

	7.36.2.7 reserved
	7.36.2.8 source
7.37 fc2Sys	stemInfo Struct Reference
7.37.1	Detailed Description
7.37.2	Field Documentation
	7.37.2.1 byteOrder
	7.37.2.2 cpuDescription
	7.37.2.3 driverList
	7.37.2.4 gpuDescription
	7.37.2.5 libraryList
	7.37.2.6 numCpuCores
	7.37.2.7 osDescription
	7.37.2.8 osType
	7.37.2.9 reserved
	7.37.2.10 screenHeight
	7.37.2.11 screenWidth
	7.37.2.12 sysMemSize
7.38 fc2TIF	FOption Struct Reference
7.38.1	Detailed Description
7.38.2	Field Documentation
	7.38.2.1 compression
	7.38.2.2 reserved
7.39 fc2Tim	eStamp Struct Reference
7.39.1	Detailed Description
7.39.2	Field Documentation
	7.39.2.1 cycleCount
	7.39.2.2 cycleOffset
	7.39.2.3 cycleSeconds
	7.39.2.4 microSeconds
	7.39.2.5 reserved
	7.39.2.6 seconds
	gerDelay Struct Reference
7.40.1	Detailed Description
7.40.2	Field Documentation

CONTENTS xxi

	7.40.2.1 absControl
	7.40.2.2 absValue
	7.40.2.3 autoManualMode
	7.40.2.4 onePush
	7.40.2.5 onOff
	7.40.2.6 present
	7.40.2.7 reserved
	7.40.2.8 type
	7.40.2.9 valueA
	7.40.2.10 valueB
7.41 fc2Trig	ggerDelayInfo Struct Reference
7.41.1	Detailed Description
7.41.2	Field Documentation
	7.41.2.1 absMax
	7.41.2.2 absMin
	7.41.2.3 absValSupported
	7.41.2.4 autoSupported
	7.41.2.5 manualSupported
	7.41.2.6 max
	7.41.2.7 min
	7.41.2.8 onePushSupported
	7.41.2.9 onOffSupported
	7.41.2.10 present
	7.41.2.11 pUnitAbbr
	7.41.2.12 pUnits
	7.41.2.13 readOutSupported
	7.41.2.14 reserved
	7.41.2.15 type
7.42 fc2Trig	ggerMode Struct Reference
7.42.1	Detailed Description
7.42.2	Field Documentation
	7.42.2.1 mode
	7.42.2.2 onOff
	7.42.2.3 parameter

xxii CONTENTS

			7.42.2.4	polarity
			7.42.2.5	reserved
			7.42.2.6	source
	7.43	fc2Trigg	gerModeIn	fo Struct Reference
		7.43.1	Detailed I	Description
		7.43.2	Field Doo	umentation
			7.43.2.1	modeMask
			7.43.2.2	onOffSupported
			7.43.2.3	polaritySupported
			7.43.2.4	present
			7.43.2.5	readOutSupported
			7.43.2.6	reserved
			7.43.2.7	softwareTriggerSupported
			7.43.2.8	sourceMask
			7.43.2.9	valueReadable
	7.44	fc2Vers	ion Struct	Reference
		7.44.1	Detailed I	Description
		7.44.2	Field Doo	umentation
			7.44.2.1	build
			7.44.2.2	major
			7.44.2.3	minor
			7.44.2.4	type
•	Tile I	D = =		105
8	8.1		entation	<b>195</b> File Reference
	0.1	8.1.1		Documentation
		0.1.1	8.1.1.1	fc2CreateContext
			8.1.1.2	
				fc2CreateGigEContext
			8.1.1.3	fc2DeregisterAllEvents
			8.1.1.4	fc2DeregisterEvent
			8.1.1.5	fc2DestroyContext
			8.1.1.6	fc2GetCycleTime
			8.1.1.7	fc2GetStats
			8.1.1.8	fc2RegisterAllEvents

		8.1.1.9	fc2RegisterEvent
		8.1.1.10	ResetStats
8.2	FlyCap	ture2Defs_	_C.h File Reference
	8.2.1	Enumera	tion Type Documentation
		8.2.1.1	fc2ByteOrder
		8.2.1.2	fc2NodeType
		8.2.1.3	fc2OSType
		8.2.1.4	fc2PortType
		8.2.1.5	fc2StatisticsChannel
8.3	FlyCap	ture2GUI_	C.h File Reference
	8.3.1	Function	Documentation
		8.3.1.1	fc2CreateGUIContext
		8.3.1.2	fc2DestroyGUIContext
		8.3.1.3	fc2Disonnect
		8.3.1.4	fc2GUIConnect
		8.3.1.5	fc2GUIDisconnect
		8.3.1.6	fc2Hide
		8.3.1.7	fc2IsVisible
		8.3.1.8	fc2Show
		8.3.1.9	fc2ShowModal
8.4	FlyCap	ture2Inter	nal_C.h File Reference
	8.4.1	Function	Documentation
		8.4.1.1	IsContextValid
		8.4.1.2	IsGuiContextValid
		8.4.1.3	SyncCppImageToStruct
8.5	FlyCap	ture2Platfo	orm_C.h File Reference
	8.5.1	Define Do	ocumentation
		8.5.1.1	FLYCAPTURE2_C_API
		8.5.1.2	FLYCAPTURE2_C_CALL_CONVEN
8.6	FlyCap	ture2Priva	te_C.h File Reference
	8.6.1	Function	Documentation
		8.6.1.1	GetInternal
8.7	FlyCap	ture2Video	o_C.h File Reference
8.8	FlyCap	ture2Video	DDefs_C.h File Reference

xxiv CONTENTS

8.9	Licensi	ng.dox File	Reference
8.10	MultiSy	ncLibrary_	C.h File Reference
	8.10.1	Function	Documentation
		8.10.1.1	syncCreateContext
		8.10.1.2	syncDestroyContext
		8.10.1.3	syncDisableCrossPCSynchronization
		8.10.1.4	syncEnableCrossPCSynchronization
		8.10.1.5	syncGetStatus
		8.10.1.6	syncGetTimeSinceSynced
		8.10.1.7	syncIsTimingBusConnected
		8.10.1.8	syncQueryCrossPCSynchronizationSetting 226
		8.10.1.9	syncRescanMasterTimingBus
		8.10.1.10	syncStart
		8.10.1.11	syncStop
8.11	MultiSy	ncLibrary	Defs_C.h File Reference
	8.11.1	Define Do	ocumentation
		8.11.1.1	FALSE
		8.11.1.2	FULL_32BIT_VALUE
		8.11.1.3	MAX_STRING_LENGTH
		8.11.1.4	TRUE
	8.11.2	Typedef D	Occumentation
		8.11.2.1	BOOL
		8.11.2.2	syncContext
	8.11.3	Enumerat	ion Type Documentation
		8.11.3.1	syncError
		8.11.3.2	syncMessage
8.12	MultiSy	ncLibraryF	Platform_C.h File Reference
	8.12.1	Define Do	ocumentation
		8.12.1.1	MULTISYNCLIBRARY_C_API
		8.12.1.2	MULTISYNCLIBRARY_C_CALL_CONVEN 229

# **Software Licensing Information**

Component	License
FlyCapture2	Copyright © 2017 FLIR Integrated
	Imaging Solutions, Inc. All Rights
	Reserved. This software is the
	confidential and proprietary information
	of FLIR Integrated Imaging Solutions,
	Inc. ("Confidential Information"). You
	shall not disclose such Confidential
	Information and shall use it only in
	accordance with the terms of the
	license agreement you entered into with
	FLIR Integrated Imaging Solutions, Inc.
	(FLIR).
	FLIR MAKES NO REPRESENTATIONS
	OR WARRANTIES ABOUT THE
	SUITABILITY OF THE SOFTWARE,
	EITHER EXPRESSED OR IMPLIED,
	INCLUDING, BUT NOT LIMITED TO,
	THE IMPLIED WARRANTIES OF
	MERCHANTABILITY, FITNESS FOR A
	PARTICULAR PURPOSE, OR
	NON-INFRINGEMENT. FLIR SHALL
	NOT BE LIABLE FOR ANY DAMAGES
	SUFFERED BY LICENSEE AS A
	RESULT OF USING, MODIFYING OR
	DISTRIBUTING THIS SOFTWARE OR
	ITS DERIVATIVES.
AdapterList	The Code Project Open License
	(CPOL)
	http://www.codeproject
	com/info/cpol10.aspx
Boost	Boost Software License
	http://www.boost
	org/users/license.html
FFMPEG	LGPv2.1 License https://www
Function	ffmpeg.org/legal.html
FreeImage	Freelmage public license http-
	://freeimage.sourceforge
GTK	net/freeimage-license.txt LGPv2.1 License
GIN	
	<pre>http://www.gnu org/licenses/old-licenses/lqpl-2.</pre>
	org/licenses/old-licenses/lgpl-2.
Libusb	LGPLv2.1 License
LIDUSU	
	http://www.gpu -
	http://www.gnu
	org/licenses/old-licenses/lgpl-2.
Libraw1394	<pre>org/licenses/old-licenses/lgpl-2. 1.txt</pre>
Libraw1394	<pre>org/licenses/old-licenses/lgpl-2. 1.txt LGPLv2.0 License</pre>
Libraw1394	<pre>org/licenses/old-licenses/lgpl-2. 1.txt LGPLv2.0 License http://www.gnu</pre>
	<pre>org/licenses/old-licenses/lgpl-2. 1.txt LGPLv2.0 License</pre>

Table 1.1: License table

## **Deprecated List**

Global fc2Disonnect (fc2GuiContext context) \_\_attribute\_\_((deprecated))

This method is deprecated and will be removed in a future FlyCapture2 release. Please use fc2GUIDisconnect instead.

#### **Module Index**

#### 3.1 Modules

Here	19 2	a liet	ot all	modi	IIPS.

Bus Manager Operation
Connection and Image Retrieval
Information and Properties
General Purpose Input / Output
Trigger
Strobe
Look Up Table
Memory Channels
Register Operation
DCAM Formats
Format7
GVCP Register Operation
GigE property manipulation
GigE image settings
GigE image binning settings
GigE image stream configuration
Image Operation
Image Statistics Operation
TopologyNode Operation
Utilities
TypeDefs
Enumerations
GigE specific enumerations
Structures
GigE specific structures
IIDC specific structures
Image saving structures
Video saving structures
Video Recording Operation 127

6 Module Index

#### **Data Structure Index**

#### 4.1 Data Structures

Here are the data structures with brief descriptions:

fc2AVIOption	
Options for saving AVI files	33
fc2BMPOption	
Options for saving Bitmap image	34
fc2CameraInfo	
Camera information	34
fc2CameraStats	
Camera diagnostic information	10
fc2Config	
Configuration for a camera	12
fc2ConfigROM	
Camera configuration ROM	15
fc2EmbeddedImageInfo	
Properties of the possible embedded image information 14	17
fc2EmbeddedImageInfoProperty	
Properties of a single embedded image info property	
fc2EventCallbackData15	50
fc2EventOptions	
Options for enabling device event registration	51
fc2Format7ImageSettings	
Format 7 image settings	52
fc2Format7Info	
Format 7 information for a single mode	54
fc2Format7PacketInfo	
Format 7 packet information	56
fc2GigEConfig	
Configuration for a GigE camera	57
fc2GigEImageSettings	
Image settings for a GigE camera	58

fc2GigEImageSettingsInfo
Format 7 information for a single mode
A GigE property
fc2GigEStreamChannel
Information about a single GigE stream channel
fc2H264Option
Options for saving H264 files
fc2Image
fc2ImageMetadata
Metadata related to an image
fc2InternalContext
fc2InternalGuiContext
fc2InternalImageCallback
fc2IPAddress
IPv4 address
fc2JPEGOption
Options for saving JPEG image
fc2JPG2Option Options for acting IREC2000 image
Options for saving JPEG2000 image
fc2LUTData Information about the camera's look up table
fc2MACAddress
MAC address
fc2MJPGOption
Options for saving MJPG files
fc2PGMOption
Options for saving PGM images
fc2PGRGuid
A GUID to the camera
fc2PNGOption
Options for saving PNG images
fc2PPMOption
Options for saving PPM images
fc2StrobeControl
A camera strobe
fc2StrobeInfo
A camera strobe property
fc2SystemInfo
Description of the system
fc2TIFFOption
Options for saving TIFF images
fc2TimeStamp
Timestamp information
A specific camera property
fc2TriggerDelayInfo
Information about a specific camera property
fc2TriggerMode
A camera trigger

4.1 Data Structures	9

fc2TriggerModeInfo	
Information about a camera trigger property	190
fc2Version	
The current version of the library	192

## **Chapter 5**

## File Index

## 5.1 File List

Here is a list of all files with brief descriptions:

/Capture2_C.h	95
/Capture2Defs_C.h	10
/Capture2GUI_C.h	18
/Capture2Internal_C.h	21
/Capture2Platform_C.h	21
/Capture2Private_C.h	22
/Capture2Video_C.h	22
/Capture2VideoDefs_C.h	23
ultiSyncLibrary_C.h	23
ultiSyncLibraryDefs_C.h	27
ultiSyncl ibraryPlatform C.h. 29	29

12 File Index

## **Chapter 6**

## **Module Documentation**

## 6.1 Bus Manager Operation

The functions in this section provide access to BusManager operations.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2FireBusReset (fc2Context context, fc2PGR-Guid \*pGuid)

Fire a bus reset.

FLYCAPTURE2\_C\_API fc2Error fc2GetNumOfCameras (fc2Context context, unsigned int \*pNumCameras)

Gets the number of cameras attached to the PC.

FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromIPAddress (fc2Context context, fc2IPAddress ipAddress, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a camera with the specified IPv4 address.

• FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromIndex (fc2Context context, unsigned int index, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromSerialNumber (fc2Context context, unsigned int serialNumber, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraSerialNumberFromIndex (fc2-Context context, unsigned int index, unsigned int \*pSerialNumber)

Gets the serial number of the camera with the specified index.

FLYCAPTURE2\_C\_API fc2Error fc2GetInterfaceTypeFromGuid (fc2Context context, fc2PGRGuid \*pGuid, fc2InterfaceType \*pInterfaceType)

Gets the interface type associated with a PGRGuid.

FLYCAPTURE2\_C\_API fc2Error fc2GetNumOfDevices (fc2Context context, unsigned int \*pNumDevices)

Gets the number of devices.

• FLYCAPTURE2\_C\_API fc2Error fc2GetDeviceFromIndex (fc2Context context, unsigned int index, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a device.

 FLYCAPTURE2\_C\_API fc2Error fc2ReadPhyRegister (fc2Context context, fc2-PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int \*pValue)

Read a phy register on the specified device.

 FLYCAPTURE2\_C\_API fc2Error fc2WritePhyRegister (fc2Context context, fc2-PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)

Write a phy register on the specified device.

 FLYCAPTURE2\_C\_API fc2Error fc2GetUsbLinkInfo (fc2Context context, fc2PG-RGuid guid, unsigned int \*pValue)

Read usb link info for the port that the specified device is connected to.

 FLYCAPTURE2\_C\_API fc2Error fc2GetUsbPortStatus (fc2Context context, fc2-PGRGuid guid, unsigned int \*pValue)

Read usb port status for the port that the specified device is connected to.

 FLYCAPTURE2\_C\_API fc2Error fc2GetTopology (fc2Context context, fc2-TopologyNodeContext \*pTopologyNodeContext)

Gets the topology information for the PC.

FLYCAPTURE2\_C\_API fc2Error fc2RegisterCallback (fc2Context context, fc2-BusEventCallback enumCallback, fc2BusCallbackType callbackType, void \*p-Parameter, fc2CallbackHandle \*pCallbackHandle)

Register a callback function that will be called when the specified callback event occurs.

 FLYCAPTURE2\_C\_API fc2Error fc2UnregisterCallback (fc2Context context, fc2-CallbackHandle callbackHandle)

Unregister a callback function.

FLYCAPTURE2\_C\_API fc2Error fc2RescanBus (fc2Context context)
 Force a rescan of the buses.

FLYCAPTURE2\_C\_API fc2Error fc2ForceIPAddressToCamera (fc2Context context, fc2MACAddress macAddress, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

• FLYCAPTURE2 C API fc2Error fc2ForceAllIPAddressesAutomatically ()

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

 FLYCAPTURE2\_C\_API fc2Error fc2ForceIPAddressAutomatically (unsigned int serialNumber)

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

• FLYCAPTURE2\_C\_API fc2Error fc2DiscoverGigECameras (fc2Context context, fc2CameraInfo \*gigECameras, unsigned int \*arraySize)

Discover all cameras connected to the network even if they reside on a different subnet.

 FLYCAPTURE2\_C\_API fc2Error fc2IsCameraControlable (fc2Context context, fc2PGRGuid \*pGuid, BOOL \*pControlable)

Query whether a GigE camera is controllable.

## 6.1.1 Detailed Description

The functions in this section provide access to BusManager operations.

## 6.1.2 Function Documentation

6.1.2.1 FLYCAPTURE2\_C\_API fc2Error fc2DiscoverGigECameras ( fc2Context context, fc2CameraInfo \* gigECameras, unsigned int \* arraySize )

Discover all cameras connected to the network even if they reside on a different subnet.

This is useful in situations where a GigE camera is using Persistent IP and the application's subnet is different from the device subnet. After discovering the camera, it is easy to use ForceIPAddressToCamera() to set a different IP configuration.

#### **Parameters**

context	The fc2Context to be used.
gigE-	Pointer to an array of CameraInfo structures.
Cameras	
arraySize	Size of the array. Number of discovered cameras is returned in the
	same value.

## Returns

An Error indicating the success or failure of the function. If the error is PGRERR-OR\_BUFFER\_TOO\_SMALL then arraySize will contain the minimum size needed for gigECameras array.

6.1.2.2 FLYCAPTURE2\_C\_API fc2Error fc2FireBusReset ( fc2Context context, fc2PGRGuid \* pGuid )

Fire a bus reset.

The actual bus reset is only fired for the specified 1394 bus, but it will effectively cause a global bus reset for the library.

COI	ntext	The fc2Context to be used.
p	Guid	PGRGuid of the camera or the device to cause bus reset.

An Error indicating the success or failure of the function.

## 6.1.2.3 FLYCAPTURE2\_C\_API fc2Error fc2ForceAllIPAddressesAutomatically ( )

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

This is useful in situations where GigE Vision cameras are using IP addresses in a subnet different from the host's subnet.

### Returns

An Error indicating the success or failure of the function.

## 6.1.2.4 FLYCAPTURE2\_C\_API fc2Error fc2ForcelPAddressAutomatically ( unsigned int serialNumber )

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

This is useful in situations where GigE Vision cameras are using IP addresses in a subnet different from the host's subnet.

## **Returns**

An Error indicating the success or failure of the function.

# 6.1.2.5 FLYCAPTURE2\_C\_API fc2Error fc2ForcelPAddressToCamera ( fc2Context context, fc2MACAddress macAddress, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway )

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

This is useful in situations where a GigE Vision camera is using Persistent IP and the application's subnet is different from the device subnet.

context	The fc2Context to be used.
macAddress	MAC address of the camera.
ipAddress	IP address to set on the camera.
subnetMask	Subnet mask to set on the camera.
default-	Default gateway to set on the camera.
Gateway	

An Error indicating the success or failure of the function.

6.1.2.6 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromIndex ( fc2Context context, unsigned int index, fc2PGRGuid \* pGuid )

Gets the PGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the index and is used to identify the camera during a fc2Connect() call.

### **Parameters**

context	The fc2Context to be used.
index	Zero based index of camera.
pGuid	Unique PGRGuid for the camera.

### **Returns**

A fc2Error indicating the success or failure of the function.

6.1.2.7 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromIPAddress ( fc2Context context, fc2IPAddress ipAddress, fc2PGRGuid \* pGuid )

Gets the PGRGuid for a camera with the specified IPv4 address.

### **Parameters**

context	The fc2Context to be used.
ipAddress	IP address to get GUID for.
pGuid	Unique PGRGuid for the camera.

## Returns

A fc2Error indicating the success or failure of the function.

6.1.2.8 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromSerialNumber ( fc2Context context, unsigned int serialNumber, fc2PGRGuid \* pGuid )

Gets the PGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the serial number and is used to identify the camera during a fc2Connect() call.

### **Parameters**

context	The fc2Context to be used.
serial-	Serial number of camera.
Number	
pGuid	Unique PGRGuid for the camera.

## Returns

A fc2Error indicating the success or failure of the function.

6.1.2.9 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraSerialNumberFromIndex ( fc2Context context, unsigned int index, unsigned int \* pSerialNumber )

Gets the serial number of the camera with the specified index.

### **Parameters**

context	The fc2Context to be used.
index	Zero based index of desired camera.
pSerial-	Serial number of camera.
Number	

## Returns

A fc2Error indicating the success or failure of the function.

6.1.2.10 FLYCAPTURE2\_C\_API fc2Error fc2GetDeviceFromIndex ( fc2Context context, unsigned int index, fc2PGRGuid \* pGuid )

Gets the PGRGuid for a device.

It uniquely identifies the device specified by the index.

## **Parameters**

context	The fc2Context to be used.
index	Zero based index of device.
pGuid	Unique PGRGuid for the device.

## See also

fc2GetNumOfDevices()

## Returns

6.1.2.11 FLYCAPTURE2\_C\_API fc2Error fc2GetInterfaceTypeFromGuid ( fc2Context context, fc2PGRGuid \* pGuid, fc2InterfaceType \* pInterfaceType )

Gets the interface type associated with a PGRGuid.

This is useful in situations where there is a need to enumerate all cameras for a particular interface.

### **Parameters**

context	The fc2Context to be used.
pGuid	The PGRGuid to get the interface for.
pInterface-	The interface type of the PGRGuid.
Туре	

### **Returns**

6.1.2.12 FLYCAPTURE2\_C\_API fc2Error fc2GetNumOfCameras ( fc2Context context, unsigned int \* pNumCameras )

Gets the number of cameras attached to the PC.

## **Parameters**

context	The fc2Context to be used.
pNum-	Number of cameras detected.
Cameras	

## **Returns**

A fc2Error indicating the success or failure of the function.

6.1.2.13 FLYCAPTURE2\_C\_API fc2Error fc2GetNumOfDevices ( fc2Context context, unsigned int \* pNumDevices )

Gets the number of devices.

This may include hubs, host controllers and other hardware devices (including cameras).

context	The fc2Context to be used.
pNum-	The number of devices found.
Devices	

An Error indicating the success or failure of the function.

## 6.1.2.14 FLYCAPTURE2\_C\_API fc2Error fc2GetTopology ( fc2Context context, fc2TopologyNodeContext \* pTopologyNodeContext )

Gets the topology information for the PC.

### **Parameters**

context	The fc2Context to be used.
pTopology-	A Topology Node context that will contain the topology information
Node-	
Context	

## Returns

An Error indicating the success or failure of the function.

## 6.1.2.15 FLYCAPTURE2\_C\_API fc2Error fc2GetUsbLinkInfo ( fc2Context context, fc2PGRGuid guid, unsigned int \* pValue )

Read usb link info for the port that the specified device is connected to.

## **Parameters**

context	The fc2Context to be used.
guid	Unique PGRGuid for the device.
pValue	Value read from the card register.

## Returns

An Error indicating the success or failure of the function.

## 6.1.2.16 FLYCAPTURE2\_C\_API fc2Error fc2GetUsbPortStatus ( fc2Context context, fc2PGRGuid guid, unsigned int \* pValue )

Read usb port status for the port that the specified device is connected to.

ſ	context	The fc2Context to be used.
	guid	Unique PGRGuid for the device.
	pValue	Value read from the card register.

An Error indicating the success or failure of the function.

6.1.2.17 FLYCAPTURE2\_C\_API fc2Error fc2lsCameraControlable ( fc2Context context, fc2PGRGuid \* pGuid, BOOL \* pControlable )

Query whether a GigE camera is controllable.

### **Parameters**

context	The fc2Context to be used.
pGuid	Unique PGRGuid for the camera.
p-	True indicates camera is controllable
Controllable	

### **Returns**

A fc2Error indicating the success or failure of the function.

6.1.2.18 FLYCAPTURE2\_C\_API fc2Error fc2ReadPhyRegister ( fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int \* pValue\*)

Read a phy register on the specified device.

The full address to be read from is determined by the page, port and address.

## **Parameters**

context	The fc2Context to be used.
guid	Unique PGRGuid for the device.
page	Page to read from.
port	Port to read from.
address	Address to read from.
pValue	Value read from the phy register.

### **Returns**

An Error indicating the success or failure of the function.

6.1.2.19 FLYCAPTURE2\_C\_API fc2Error fc2RegisterCallback ( fc2Context context, fc2BusEventCallback enumCallback, fc2BusCallbackType callbackType, void \* pParameter, fc2CallbackHandle \* pCallbackHandle )

Register a callback function that will be called when the specified callback event occurs.

### **Parameters**

context	The fc2Context to be used.
enum-	Pointer to function that will receive the callback.
Callback	
callbackType	Type of callback to register for.
pParameter	Callback parameter to be passed to callback.
pCallback-	Unique callback handle used for unregistering callback.
Handle	

### Returns

A fc2Error indicating the success or failure of the function.

## 6.1.2.20 FLYCAPTURE2\_C\_API fc2Error fc2RescanBus ( fc2Context context )

Force a rescan of the buses.

This does not trigger a bus reset. The camera objects will be invalidated only if the camera network topology is changed (ie. a camera is disconnected or added)

### Returns

An Error indicating the success or failure of the function.

## 6.1.2.21 FLYCAPTURE2\_C\_API fc2Error fc2UnregisterCallback ( fc2Context context, fc2CallbackHandle callbackHandle )

Unregister a callback function.

## **Parameters**

context	The fc2Context to be used.
	Unique callback handle.
Handle	4

### Returns

A fc2Error indicating the success or failure of the function.

6.1.2.22 FLYCAPTURE2\_C\_API fc2Error fc2WritePhyRegister ( fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value )

Write a phy register on the specified device.

The full address to be written to is determined by the page, port and address.

## **Parameters**

context	The fc2Context to be used.
guid	Unique PGRGuid for the device.
page	Page to write to.
port	Port to write to.
address	Address to write to.
value	Value to write to phy register.

## Returns

## 6.2 Connection and Image Retrieval

These functions deal with connections and image retrieval from the camera.

### **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2Connect (fc2Context context, fc2PGRGuid \*quid)

Connects the fc2Context to the camera specified by the GUID.

• FLYCAPTURE2\_C\_API fc2Error fc2Disconnect (fc2Context context)

Disconnects the fc2Context from the camera.

FLYCAPTURE2 C API BOOL fc2lsConnected (fc2Context context)

Checks if the fc2Context is connected to a physical camera specified by a GUID.

 FLYCAPTURE2\_C\_API fc2Error fc2SetCallback (fc2Context context, fc2Image-EventCallback pCallbackFn, void \*pCallbackData)

Sets the callback data to be used on completion of image transfer.

FLYCAPTURE2\_C\_API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

 FLYCAPTURE2\_C\_API fc2Error fc2StartCaptureCallback (fc2Context context, fc2ImageEventCallback pCallbackFn, void \*pCallbackData)

Starts isochronous image capture.

 FLYCAPTURE2\_C\_API fc2Error fc2StartSyncCapture (unsigned int num-Cameras, fc2Context \*pContexts)

Starts synchronized isochronous image capture on multiple cameras.

 FLYCAPTURE2\_C\_API fc2Error fc2StartSyncCaptureCallback (unsigned int numCameras, fc2Context \*pContexts, fc2ImageEventCallback \*pCallbackFns, void \*\*pCallbackDataArray)

Starts synchronized isochronous image capture on multiple cameras.

 FLYCAPTURE2\_C\_API fc2Error fc2RetrieveBuffer (fc2Context context, fc2lmage \*plmage)

Retrieves the next image object containing the next image.

FLYCAPTURE2\_C\_API fc2Error fc2StopCapture (fc2Context context)

Stops isochronous image transfer and cleans up all associated resources.

 FLYCAPTURE2\_C\_API fc2Error fc2WaitForBufferEvent (fc2Context context, fc2lmage \*plmage, unsigned int eventNumber)

Retrieves the next image event containing the next part of the image.

FLYCAPTURE2\_C\_API fc2Error fc2SetUserBuffers (fc2Context context, unsigned char \*const ppMemBuffers, int size, int nNumBuffers)

Specify user allocated buffers to use as image data buffers.

 FLYCAPTURE2\_C\_API fc2Error fc2GetConfiguration (fc2Context context, fc2-Config \*config)

Get the configuration associated with the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetConfiguration (fc2Context context, fc2-Config \*config)

Set the configuration associated with the camera.

## 6.2.1 Detailed Description

These functions deal with connections and image retrieval from the camera.

## 6.2.2 Function Documentation

6.2.2.1 FLYCAPTURE2\_C\_API fc2Error fc2Connect ( fc2Context context, fc2PGRGuid \* guid )

Connects the fc2Context to the camera specified by the GUID.

Be aware that calling fc2CreateGUIContext() releases the CCP acquired for GigE cameras in fc2Connect(). Consider calling fc2Connect() after fc2CreateGUIContext().

### **Parameters**

context	The fc2Context to be used.
guid	The unique identifier for a specific camera on the PC.

### Returns

A fc2Error indicating the success or failure of the function.

## 6.2.2.2 FLYCAPTURE2\_C\_API fc2Error fc2Disconnect ( fc2Context context )

Disconnects the fc2Context from the camera.

This allows another physical camera specified by a GUID to be connected to the fc2-Context.

## See also

fc2Connect()

## **Parameters**

context	The fc2Context to be used.

### Returns

A fc2Error indicating the success or failure of the function.

## 6.2.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetConfiguration ( fc2Context context, fc2Config \* config )

Get the configuration associated with the camera.

## See also

fc2SetConfiguration()

### **Parameters**

context	The fc2Context to be used.
config	Pointer to the configuration structure to be filled.

## Returns

A fc2Error indicating the success or failure of the function.

## 6.2.2.4 FLYCAPTURE2\_C\_API BOOL fc2lsConnected ( fc2Context context )

Checks if the fc2Context is connected to a physical camera specified by a GUID.

## See also

```
fc2Connect()
fc2Disconnect()
```

## **Parameters**

context	The fc2Context to be used.

## Returns

Whether fc2Connect() was called on the fc2Context.

## 6.2.2.5 FLYCAPTURE2\_C\_API fc2Error fc2RetrieveBuffer ( fc2Context context, fc2Image \* plmage )

Retrieves the next image object containing the next image.

## See also

```
fc2StartCapture()
fc2StopCapture()
```

context	The fc2Context to be used.
	Pointer to fc2Image to store image data.

A fc2Error indicating the success or failure of the function.

6.2.2.6 FLYCAPTURE2\_C\_API fc2Error fc2SetCallback ( fc2Context context, fc2ImageEventCallback pCallbackFn, void \* pCallbackData )

Sets the callback data to be used on completion of image transfer.

To clear the current stored callback data, pass in NULL for both callback arguments.

## See also

fc2StartCapture()

## **Parameters**

context	The fc2Context to be used.
pCallbackFn	A function to be called when a new image is received.
pCallback-	A pointer to data that can be passed to the callback function.
Data	

## **Returns**

A fc2Error indicating the success or failure of the function.

6.2.2.7 FLYCAPTURE2\_C\_API fc2Error fc2SetConfiguration ( fc2Context context, fc2Config \* config )

Set the configuration associated with the camera.

## See also

fc2GetConfiguration()

context	The fc2Context to be used.
config	Pointer to the configuration structure to be used.

A fc2Error indicating the success or failure of the function.

6.2.2.8 FLYCAPTURE2\_C\_API fc2Error fc2SetUserBuffers ( fc2Context context, unsigned char \*const ppMemBuffers, int size, int nNumBuffers )

Specify user allocated buffers to use as image data buffers.

To prevent image tearing, the size of each buffer should be equal to ((unsigned int)(bufferSize + packetSize - 1)/packetSize) \* packetSize. The total size should be (size \* numBuffers) or larger. The packet Size that should be used differs between interfaces: Firewire: Use the Format7 packet size. Usb2: First round to Format7 packet size then round to 512 bytes. Usb3: Use a packet size of 1024 bytes. GigE: No need to do any rounding on GigE

### See also

```
fc2StartCapture()
fc2RetrieveBuffer()
fc2StopCapture()
```

### **Parameters**

context	The fc2Context to be used.
ррМет-	Pointer to memory buffers to be written to. The size of the data should
Buffers	be equal to (size * numBuffers) or larger.
size	The size of each buffer (in bytes).
nNum-	Number of buffers in the array.
Buffers	

## Returns

A fc2Error indicating the success or failure of the function.

## 6.2.2.9 FLYCAPTURE2\_C\_API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera.

## See also

```
fc2RetrieveBuffer()
fc2StartSyncCapture()
fc2StopCapture()
```

## **Parameters**

context	The fc2Context to be used.

### **Returns**

A fc2Error indicating the success or failure of the function.

6.2.2.10 FLYCAPTURE2\_C\_API fc2Error fc2StartCaptureCallback ( fc2Context context, fc2ImageEventCallback pCallbackFn, void \* pCallbackData )

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera. The callback function is called when a new image is received from the camera.

### See also

```
fc2RetrieveBuffer()
fc2StartSyncCapture()
fc2StopCapture()
```

## **Parameters**

context	The fc2Context to be used.
pCallbackFn	A function to be called when a new image is received.
pCallback-	A pointer to data that can be passed to the callback function. A NULL
Data	pointer is acceptable.

## Returns

A fc2Error indicating the success or failure of the function.

6.2.2.11 FLYCAPTURE2\_C\_API fc2Error fc2StartSyncCapture ( unsigned int *numCameras*, fc2Context \* *pContexts* )

Starts synchronized isochronous image capture on multiple cameras.

This function is only used for firewire cameras.

## See also

```
fc2RetrieveBuffer()
fc2StartCapture()
fc2StopCapture()
```

num-	Number of fc2Contexts in the ppCameras array.
Cameras	
pContexts	Array of fc2Contexts.

A fc2Error indicating the success or failure of the function.

6.2.2.12 FLYCAPTURE2\_C\_API fc2Error fc2StartSyncCaptureCallback ( unsigned int numCameras, fc2Context \* pContexts, fc2ImageEventCallback \* pCallbackFns, void \*\* pCallbackDataArray )

Starts synchronized isochronous image capture on multiple cameras.

This function is only used for firewire cameras.

### See also

fc2RetrieveBuffer()
fc2StartCapture()
fc2StopCapture()

## **Parameters**

num-	Number of fc2Contexts in the ppCameras array.
Cameras	
pContexts	Array of fc2Contexts.
pCallback-	Array of callback functions for each camera.
Fns	
pCallback-	Array of callback data pointers.
DataArray	

## Returns

A fc2Error indicating the success or failure of the function.

## 6.2.2.13 FLYCAPTURE2\_C\_API fc2Error fc2StopCapture ( fc2Context context )

Stops isochronous image transfer and cleans up all associated resources.

## See also

fc2StartCapture()
fc2RetrieveBuffer()

## **Parameters**

context	The fc2Context to be used.

## Returns

A fc2Error indicating the success or failure of the function.

6.2.2.14 FLYCAPTURE2\_C\_API fc2Error fc2WaitForBufferEvent ( fc2Context context, fc2Image \* plmage, unsigned int eventNumber )

Retrieves the next image event containing the next part of the image.

## See also

```
fc2StartCapture()
fc2RetrieveBuffer()
fc2StopCapture()
```

## **Parameters**

context	The fc2Context to be used.
plmage	Pointer to fc2Image to store image data.
event-	The event number to wait for.
Number	

## Returns

## 6.3 Information and Properties

These functions deal with information and properties can be retrieved from the camera.

### **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraInfo (fc2Context context, fc2-CameraInfo \*pCameraInfo)

Retrieves information from the camera such as serial number, model name and other camera information.

 FLYCAPTURE2\_C\_API fc2Error fc2GetPropertyInfo (fc2Context context, fc2-PropertyInfo \*propInfo)

Retrieves information about the specified camera property.

 FLYCAPTURE2\_C\_API fc2Error fc2GetProperty (fc2Context context, fc2-Property \*prop)

Reads the settings for the specified property from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetProperty (fc2Context context, fc2-Property \*prop)

Writes the settings for the specified property to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetPropertyBroadcast (fc2Context context, fc2Property \*prop)

Writes the settings for the specified property to the camera.

## 6.3.1 Detailed Description

These functions deal with information and properties can be retrieved from the camera.

## 6.3.2 Function Documentation

6.3.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraInfo ( fc2Context context, fc2CameraInfo \* pCameraInfo )

Retrieves information from the camera such as serial number, model name and other camera information.

## **Parameters**

context	The fc2Context to be used.
pCameraInfo	Pointer to the camera information structure to be filled.

## Returns

6.3.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetProperty ( fc2Context context, fc2Property \* prop )

Reads the settings for the specified property from the camera.

The property type must be specified in the fc2Property structure passed into the function in order for the function to succeed. If auto is on, the integer and abs values returned may not be consistent with each other.

## See also

```
fc2GetPropertyInfo()
fc2SetProperty()
```

## **Parameters**

context	The fc2Context to be used.
prop	Pointer to the Property structure to be filled.

### **Returns**

A fc2Error indicating the success or failure of the function.

6.3.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetPropertyInfo ( fc2Context context, fc2PropertyInfo \* propInfo )

Retrieves information about the specified camera property.

The property type must be specified in the fc2PropertyInfo structure passed into the function in order for the function to succeed.

## See also

```
fc2GetProperty()
fc2SetProperty()
```

context	The fc2Context to be used.
propInfo	Pointer to the PropertyInfo structure to be filled.

A fc2Error indicating the success or failure of the function.

6.3.2.4 FLYCAPTURE2\_C\_API fc2Error fc2SetProperty ( fc2Context context, fc2Property \* prop )

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera. Use fc2GetPropertyInfo() to query which options are available for a specific property.

### See also

fc2GetPropertyInfo()
fc2GetProperty()

## **Parameters**

context	The fc2Context to be used.
prop	Pointer to the Property structure to be used.

## Returns

A fc2Error indicating the success or failure of the function.

6.3.2.5 FLYCAPTURE2\_C\_API fc2Error fc2SetPropertyBroadcast ( fc2Context context, fc2Property \* prop )

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera.

## **Parameters**

context	The fc2Context to be used.
prop	Pointer to the Property structure to be used.

## Returns

## 6.4 General Purpose Input / Output

These functions deal with general GPIO pin control on the camera.

### **Functions**

• FLYCAPTURE2\_C\_API fc2Error fc2GetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int \*pDirection)

Get the GPIO pin direction for the specified pin.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGPIOPinDirectionBroadcast (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

## 6.4.1 Detailed Description

These functions deal with general GPIO pin control on the camera.

### 6.4.2 Function Documentation

6.4.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetGPIOPinDirection ( fc2Context context, unsigned int pin, unsigned int \* pDirection\*)

Get the GPIO pin direction for the specified pin.

This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

## See also

fc2SetGPIOPinDirection()
fc2SetGPIOPinDirectionBroadcast()

## **Parameters**

context	The fc2Context to be used.
pin	Pin to get the direction for.
pDirection	Direction of the pin. 0 for input, 1 for output.

## Returns

6.4.2.2 FLYCAPTURE2\_C\_API fc2Error fc2SetGPIOPinDirection ( fc2Context context, unsigned int pin, unsigned int direction )

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

## See also

fc2GetGPIOPinDirection()
fc2SetGPIOPinDirectionBroadcast()

## **Parameters**

context	The fc2Context to be used.
pin	Pin to get the direction for.
direction	Direction of the pin. 0 for input, 1 for output.

### Returns

A fc2Error indicating the success or failure of the function.

6.4.2.3 FLYCAPTURE2\_C\_API fc2Error fc2SetGPIOPinDirectionBroadcast ( fc2Context context, unsigned int pin, unsigned int direction )

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

## See also

fc2GetGPIOPinDirection()

## **Parameters**

context	The fc2Context to be used.
pin	Pin to get the direction for.
direction	Direction of the pin. 0 for input, 1 for output.

### Returns

6.5 Trigger 37

## 6.5 Trigger

These functions deal with trigger control on the camera.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerModeInfo (fc2Context context, fc2TriggerModeInfo \*triggerModeInfo)

Retrieve trigger information from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerMode (fc2Context context, fc2-TriggerMode \*triggerMode)

Retrieve current trigger settings from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerMode (fc2Context context, fc2-TriggerMode \*triggerMode)

Set the specified trigger settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerModeBroadcast (fc2Context context, fc2TriggerMode \*triggerMode)

Set the specified trigger settings to the camera.

• FLYCAPTURE2\_C\_API fc2Error fc2FireSoftwareTrigger (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2\_C\_API fc2Error fc2FireSoftwareTriggerBroadcast (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerDelayInfo (fc2Context context, fc2TriggerDelayInfo \*triggerDelayInfo)

Retrieve trigger delay information from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerDelay (fc2Context context, fc2-TriggerDelay \*triggerDelay)

Retrieve current trigger delay settings from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerDelay (fc2Context context, fc2-TriggerDelay \*triggerDelay)

Set the specified trigger delay settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerDelayBroadcast (fc2Context context, fc2TriggerDelay \*triggerDelay)

Set the specified trigger delay settings to the camera.

## 6.5.1 Detailed Description

These functions deal with trigger control on the camera.

## 6.5.2 Function Documentation

## 6.5.2.1 FLYCAPTURE2\_C\_API fc2Error fc2FireSoftwareTrigger ( fc2Context context )

Fire the software trigger according to the DCAM specifications.

### **Parameters**

context	The fc2Context to be used.

## Returns

A fc2Error indicating the success or failure of the function.

## 6.5.2.2 FLYCAPTURE2\_C\_API fc2Error fc2FireSoftwareTriggerBroadcast ( fc2Context context )

Fire the software trigger according to the DCAM specifications.

## **Parameters**

context	The fc2Context to be used.
---------	----------------------------

## Returns

A fc2Error indicating the success or failure of the function.

## 6.5.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerDelay ( fc2Context context, fc2TriggerDelay \* triggerDelay )

Retrieve current trigger delay settings from the camera.

## See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2SetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

context	The fc2Context to be used.
triggerDelay	Structure to receive trigger delay settings.

6.5 Trigger 39

## **Returns**

A fc2Error indicating the success or failure of the function.

## 6.5.2.4 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerDelayInfo ( fc2Context context, fc2TriggerDelayInfo \* triggerDelayInfo )

Retrieve trigger delay information from the camera.

### See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

### **Parameters**

context	The fc2Context to be used.
triggerDelay-	Structure to receive trigger delay information.
Info	

## Returns

A fc2Error indicating the success or failure of the function.

## 6.5.2.5 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerMode ( fc2Context context, fc2TriggerMode \* triggerMode )

Retrieve current trigger settings from the camera.

## See also

```
fc2GetTriggerModeInfo()
fc2SetTriggerMode()
fc2SetTriggerModeBroadcast()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
```

context	The fc2Context to be used.
triggerMode	Structure to receive trigger mode settings.

A fc2Error indicating the success or failure of the function.

## 6.5.2.6 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerModeInfo ( fc2Context context, fc2TriggerModeInfo \* triggerModeInfo )

Retrieve trigger information from the camera.

### See also

```
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2SetTriggerModeBroadcast()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
```

### **Parameters**

context	The fc2Context to be used.
triggerMode-	Structure to receive trigger information.
Info	

## Returns

A fc2Error indicating the success or failure of the function.

```
6.5.2.7 FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelay ( fc2Context context, fc2TriggerDelay * triggerDelay )
```

Set the specified trigger delay settings to the camera.

## See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

context	The fc2Context to be used.
triggerDelay	Structure providing trigger delay settings.

6.5 Trigger 41

## **Returns**

A fc2Error indicating the success or failure of the function.

## 6.5.2.8 FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerDelayBroadcast ( fc2Context context, fc2TriggerDelay \* triggerDelay )

Set the specified trigger delay settings to the camera.

### See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
```

### **Parameters**

	context	The fc2Context to be used.
t	riggerDelay	Structure providing trigger delay settings.

## Returns

A fc2Error indicating the success or failure of the function.

```
6.5.2.9 FLYCAPTURE2_C_API fc2Error fc2SetTriggerMode ( fc2Context context, fc2TriggerMode * triggerMode )
```

Set the specified trigger settings to the camera.

## See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
fc2SetTriggerModeBroadcast()
```

ĺ	context	The fc2Context to be used.
ĺ	triggerMode	Structure providing trigger mode settings.

A fc2Error indicating the success or failure of the function.

6.5.2.10 FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerModeBroadcast ( fc2Context context, fc2TriggerMode \* triggerMode )

Set the specified trigger settings to the camera.

## See also

fc2GetTriggerModeInfo() fc2GetTriggerMode() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelay() fc2SetTriggerMode()

## **Parameters**

context	The fc2Context to be used.
triggerMode	Structure providing trigger mode settings.

## Returns

6.6 Strobe 43

## 6.6 Strobe

These functions deal with strobe control on the camera.

### **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2GetStrobeInfo (fc2Context context, fc2-StrobeInfo \*strobeInfo)

Retrieve strobe information from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetStrobe (fc2Context context, fc2Strobe-Control \*strobeControl)

Retrieve current strobe settings from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetStrobe (fc2Context context, fc2Strobe-Control \*strobeControl)

Set current strobe settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetStrobeBroadcast (fc2Context context, fc2StrobeControl \*strobeControl)

Set current strobe settings to the camera.

## 6.6.1 Detailed Description

These functions deal with strobe control on the camera.

## 6.6.2 Function Documentation

6.6.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetStrobe ( fc2Context context, fc2StrobeControl \* strobeControl )

Retrieve current strobe settings from the camera.

The strobe pin must be specified in the structure before being passed in to the function.

### See also

```
fc2GetStrobeInfo()
fc2SetStrobe()
fc2SetStrobeBroadcast()
```

context	The fc2Context to be used.
strobe-	Structure to receive strobe settings.
Control	

A fc2Error indicating the success or failure of the function.

## 6.6.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetStrobelnfo ( fc2Context context, fc2Strobelnfo \* strobelnfo )

Retrieve strobe information from the camera.

## See also

```
fc2GetStrobe()
fc2SetStrobeBroadcast()
```

### **Parameters**

context	The fc2Context to be used.
strobelnfo	Structure to receive strobe information.

## Returns

A fc2Error indicating the success or failure of the function.

## 6.6.2.3 FLYCAPTURE2\_C\_API fc2Error fc2SetStrobe ( fc2Context context, fc2StrobeControl \* strobeControl )

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

## See also

```
fc2GetStrobeInfo()
fc2GetStrobe()
fc2SetStrobeBroadcast()
```

## **Parameters**

context	The fc2Context to be used.
strobe-	Structure providing strobe settings.
Control	

## Returns

6.6 Strobe 45

6.6.2.4 FLYCAPTURE2\_C\_API fc2Error fc2SetStrobeBroadcast ( fc2Context context, fc2StrobeControl \* strobeControl )

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

## See also

fc2GetStrobeInfo()
fc2GetStrobe()
fc2SetStrobe()

## **Parameters**

context	The fc2Context to be used.
strobe-	Structure providing strobe settings.
Control	

## Returns

## 6.7 Look Up Table

These functions deal with Look Up Table control on the camera.

### **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2GetLUTInfo (fc2Context context, fc2LUT-Data \*pData)

Query if LUT support is available on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetLUTBankInfo (fc2Context context, unsigned int bank, BOOL \*pReadSupported, BOOL \*pWriteSupported)

Query the read/write status of a single LUT bank.

FLYCAPTURE2\_C\_API fc2Error fc2GetActiveLUTBank (fc2Context context, unsigned int \*pActiveBank)

Get the LUT bank that is currently being used.

FLYCAPTURE2\_C\_API fc2Error fc2SetActiveLUTBank (fc2Context context, unsigned int activeBank)

Set the LUT bank that will be used.

- FLYCAPTURE2\_C\_API fc2Error fc2EnableLUT (fc2Context context, BOOL on)

  Enable or disable LUT functionality on the camera.
- FLYCAPTURE2\_C\_API fc2Error fc2GetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int \*p-Entries)

Get the LUT channel settings from the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int \*p-Entries)

Set the LUT channel settings to the camera.

## 6.7.1 Detailed Description

These functions deal with Look Up Table control on the camera.

## 6.7.2 Function Documentation

6.7.2.1 FLYCAPTURE2\_C\_API fc2Error fc2EnableLUT ( fc2Context context, BOOL on )

Enable or disable LUT functionality on the camera.

## See also

fc2GetLUTInfo() fc2GetLUTChannel() fc2SetLUTChannel()

## **Parameters**

context	The fc2Context to be used.
on	Whether to enable or disable LUT.

# Returns

A fc2Error indicating the success or failure of the function.

6.7.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetActiveLUTBank ( fc2Context context, unsigned int \* pActiveBank )

Get the LUT bank that is currently being used.

For cameras with PGR LUT, the active bank is always 0.

## **Parameters**

ĺ	context	The fc2Context to be used.
	pActiveBank	The currently active bank.

## **Returns**

A fc2Error indicating the success or failure of the function.

6.7.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetLUTBankInfo ( fc2Context context, unsigned int bank, BOOL \* pReadSupported, BOOL \* pWriteSupported )

Query the read/write status of a single LUT bank.

## **Parameters**

context	The fc2Context to be used.
bank	The bank to query.
pRead-	Whether reading from the bank is supported.
Supported	
pWrite-	Whether writing to the bank is supported.
Supported	

## **Returns**

A fc2Error indicating the success or failure of the function.

6.7.2.4 FLYCAPTURE2\_C\_API fc2Error fc2GetLUTChannel ( fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int \* pEntries\*)

Get the LUT channel settings from the camera.

## See also

fc2GetLUTInfo() fc2EnableLUT() fc2SetLUTChannel()

## **Parameters**

context	The fc2Context to be used.
bank	Bank to retrieve.
channel	Channel to retrieve.
sizeEntries	Number of entries in LUT table to read.
pEntries	Array to store LUT entries.

## Returns

A fc2Error indicating the success or failure of the function.

6.7.2.5 FLYCAPTURE2\_C\_API fc2Error fc2GetLUTInfo ( fc2Context context, fc2LUTData \* pData )

Query if LUT support is available on the camera.

Note that some cameras may report support for the LUT and return an inputBitDepth of 0. In these cases use log2(numEntries) for the inputBitDepth.

## See also

fc2EnableLUT()
fc2GetLUTChannel()
fc2SetLUTChannel()

## **Parameters**

context	The fc2Context to be used.
pData	The LUT structure to be filled.

## Returns

A fc2Error indicating the success or failure of the function.

6.7.2.6 FLYCAPTURE2\_C\_API fc2Error fc2SetActiveLUTBank ( fc2Context context, unsigned int activeBank )

Set the LUT bank that will be used.

# **Parameters**

context	The fc2Context to be used.
activeBank	The bank to be set as active.

# Returns

A fc2Error indicating the success or failure of the function.

6.7.2.7 FLYCAPTURE2\_C\_API fc2Error fc2SetLUTChannel ( fc2Context *context*, unsigned int *bank*, unsigned int *channel*, unsigned int *sizeEntries*, unsigned int \* *pEntries* )

Set the LUT channel settings to the camera.

## See also

fc2GetLUTInfo() fc2EnableLUT() fc2GetLUTChannel()

## **Parameters**

context	The fc2Context to be used.
bank	Bank to set.
channel	Channel to set.
sizeEntries	Number of entries in LUT table to write. This must be the same size as
	numEntries returned by GetLutInfo().
pEntries	Array containing LUT entries to write.

# Returns

A fc2Error indicating the success or failure of the function.

# 6.8 Memory Channels

These functions deal with memory channel control on the camera.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2GetMemoryChannel (fc2Context context, unsigned int \*pCurrentChannel)

Retrieve the current memory channel from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SaveToMemoryChannel (fc2Context context, unsigned int channel)

Save the current settings to the specified current memory channel.

 FLYCAPTURE2\_C\_API fc2Error fc2RestoreFromMemoryChannel (fc2Context context, unsigned int channel)

Restore the specified current memory channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetMemoryChannelInfo (fc2Context context, unsigned int \*pNumChannels)

Query the camera for memory channel support.

FLYCAPTURE2\_C\_API fc2Error fc2GetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo \*pInfo)

Get the current status of the embedded image information register, as well as the availability of each embedded property.

FLYCAPTURE2\_C\_API fc2Error fc2SetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo \*pInfo)

Sets the on/off values of the embedded image information structure to the camera.

# 6.8.1 Detailed Description

These functions deal with memory channel control on the camera.

# 6.8.2 Function Documentation

6.8.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetEmbeddedImageInfo ( fc2Context context, fc2EmbeddedImageInfo \* pInfo )

Get the current status of the embedded image information register, as well as the availability of each embedded property.

## See also

fc2SetEmbeddedImageInfo()

context	The fc2Context to be used.
pInfo	Structure to be filled.

A fc2Error indicating the success or failure of the function.

# 6.8.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetMemoryChannel ( fc2Context context, unsigned int \* pCurrentChannel )

Retrieve the current memory channel from the camera.

## See also

```
fc2SaveToMemoryChannel()
fc2RestoreFromMemoryChannel()
fc2GetMemoryChannelInfo()
```

## **Parameters**

context	The fc2Context to be used.
pCurrent-	Current memory channel.
Channel	

## **Returns**

A fc2Error indicating the success or failure of the function.

# 6.8.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetMemoryChannelInfo ( fc2Context context, unsigned int \* pNumChannels )

Query the camera for memory channel support.

If the number of channels are 0, then memory channel support is not available.

# See also

```
fc2GetMemoryChannel()
fc2SaveToMemoryChannel()
fc2RestoreFromMemoryChannel()
```

## **Parameters**

	context	The fc2Context to be used.
ı	nNum-	Number of memory channels supported.
	pivani	Number of memory chamiles supported.
	Channels	
	0	

# Returns

A fc2Error indicating the success or failure of the function.

6.8.2.4 FLYCAPTURE2\_C\_API fc2Error fc2RestoreFromMemoryChannel ( fc2Context context, unsigned int channel )

Restore the specified current memory channel.

## See also

fc2GetMemoryChannel() fc2SaveToMemoryChannel() fc2GetMemoryChannelInfo()

# **Parameters**

context	The fc2Context to be used.
channel	Memory channel to restore from.

## Returns

A fc2Error indicating the success or failure of the function.

6.8.2.5 FLYCAPTURE2\_C\_API fc2Error fc2SaveToMemoryChannel ( fc2Context context, unsigned int channel )

Save the current settings to the specified current memory channel.

## See also

fc2GetMemoryChannel()
fc2RestoreFromMemoryChannel()
fc2GetMemoryChannelInfo()

## **Parameters**

context	The fc2Context to be used.
channel	Memory channel to save to.

# Returns

A fc2Error indicating the success or failure of the function.

6.8.2.6 FLYCAPTURE2\_C\_API fc2Error fc2SetEmbeddedImageInfo ( fc2Context context, fc2EmbeddedImageInfo \* pInfo )

Sets the on/off values of the embedded image information structure to the camera.

# See also

fc 2 Get Embedded Image In fo ()

# **Parameters**

Ī	context	The fc2Context to be used.
I	pInfo	Structure to be used.

# Returns

A fc2Error indicating the success or failure of the function.

# 6.9 Register Operation

These functions deal with register operation on the camera.

## **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegister (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2ReadRegister (fc2Context context, unsigned int address, unsigned int \*pValue)

Read the specified register from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera with broadcast.

FLYCAPTURE2\_C\_API fc2Error fc2WriteRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int \*pBuffer, unsigned int length)

Write to the specified register block on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2ReadRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int \*pBuffer, unsigned int length)

Write to the specified register block on the camera.

 FLYCAPTURE2\_C\_API const char \* fc2GetRegisterString (unsigned int register-Val)

Returns a text representation of the register value.

# 6.9.1 Detailed Description

These functions deal with register operation on the camera.

# 6.9.2 Function Documentation

6.9.2.1 FLYCAPTURE2\_C\_API const char\* fc2GetRegisterString ( unsigned int registerVal )

Returns a text representation of the register value.

## **Parameters**

registerVal The register value to query.

## Returns

A fc2Error indicating the success or failure of the function.

6.9.2.2 FLYCAPTURE2\_C\_API fc2Error fc2ReadRegister ( fc2Context context, unsigned int address, unsigned int \* pValue )

Read the specified register from the camera.

## See also

fc2WriteRegister()

## **Parameters**

context	The fc2Context to be used.
address	DCAM address to be read from.
pValue	The value that is read.

## **Returns**

A fc2Error indicating the success or failure of the function.

6.9.2.3 FLYCAPTURE2\_C\_API fc2Error fc2ReadRegisterBlock ( fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int \* pBuffer, unsigned int length )

Write to the specified register block on the camera.

# See also

fc2WriteRegisterBlock()

## **Parameters**

context	The fc2Context to be used.
addressHigh	Top 16 bits of the 48-bit absolute address to read from.
addressLow	Bottom 32 bits of the 48 bits absolute address to read from.
pBuffer	Array to store read data.
length	Size of array, in quadlets.

# Returns

A fc2Error indicating the success or failure of the function.

6.9.2.4 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegister ( fc2Context context, unsigned int address, unsigned int value )

Write to the specified register on the camera.

## See also

fc2ReadRegister()

## **Parameters**

context	The fc2Context to be used.
address	DCAM address to be written to.
value	The value to be written.

# Returns

A fc2Error indicating the success or failure of the function.

6.9.2.5 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegisterBlock ( fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int \* pBuffer, unsigned int length )

Write to the specified register block on the camera.

# See also

fc2ReadRegisterBlock()

## **Parameters**

context	The fc2Context to be used.
addressHigh	Top 16 bits of the 48-bit absolute address to write to.
addressLow	Bottom 32 bits of the 48 bits absolute address to write to.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

## Returns

A fc2Error indicating the success or failure of the function.

6.9.2.6 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegisterBroadcast ( fc2Context context, unsigned int address, unsigned int value )

Write to the specified register on the camera with broadcast.

# See also

fc2ReadRegisterBlock()

# **Parameters**

	context	The fc2Context to be used.
Γ	address	DCAM address to be written to.
Γ	value	The value to be written.

# Returns

A fc2Error indicating the success or failure of the function.

# 6.10 DCAM Formats

These functions deal with DCAM video mode and frame rate on the camera.

## **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2GetVideoModeAndFrameRateInfo (fc2-Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL \*pSupported)

Query the camera to determine if the specified video mode and frame rate is supported.

 FLYCAPTURE2\_C\_API fc2Error fc2GetVideoModeAndFrameRate (fc2Context context, fc2VideoMode \*videoMode, fc2FrameRate \*frameRate)

Get the current video mode and frame rate from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetVideoModeAndFrameRate (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

## 6.10.1 Detailed Description

These functions deal with DCAM video mode and frame rate on the camera. This is only used for firewire and usb2 cameras.

# 6.10.2 Function Documentation

6.10.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetVideoModeAndFrameRate ( fc2Context context, fc2VideoMode \* videoMode, fc2FrameRate \* frameRate )

Get the current video mode and frame rate from the camera.

If the camera is in Format7, the video mode will be VIDEOMODE\_FORMAT7 and the frame rate will be FRAMERATE\_FORMAT7.

context	The fc2Context to be used.
videoMode	Current video mode.
frameRate	Current frame rate.

6.10 DCAM Formats 59

## **Returns**

A fc2Error indicating the success or failure of the function.

6.10.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetVideoModeAndFrameRateInfo ( fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL \* pSupported )

Query the camera to determine if the specified video mode and frame rate is supported.

## **Parameters**

context	The fc2Context to be used.
videoMode	Video mode to check.
frameRate	Frame rate to check.
pSupported	Whether the video mode and frame rate is supported.

## **Returns**

A fc2Error indicating the success or failure of the function.

6.10.2.3 FLYCAPTURE2\_C\_API fc2Error fc2SetVideoModeAndFrameRate ( fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate )

Set the specified video mode and frame rate to the camera.

It is not possible to set the camera to VIDEOMODE\_FORMAT7 or FRAMERATE\_FO-RMAT7. Use the Format7 functions to set the camera into Format7.

# **Parameters**

context	The fc2Context to be used.
videoMode	Video mode to set to camera.
frameRate	Frame rate to set to camera.

## **Returns**

A fc2Error indicating the success or failure of the function.

# 6.11 Format7

These functions deal with Format7 custom image control on the camera.

## **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2GetFormat7Info (fc2Context context, fc2-Format7Info \*info, BOOL \*pSupported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

FLYCAPTURE2\_C\_API fc2Error fc2ValidateFormat7Settings (fc2Context context, fc2Format7ImageSettings \*imageSettings, BOOL \*settingsAreValid, fc2Format7PacketInfo \*packetInfo)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

FLYCAPTURE2\_C\_API fc2Error fc2GetFormat7Configuration (fc2Context context, fc2Format7ImageSettings \*imageSettings, unsigned int \*packetSize, float \*percentage)

Get the current Format7 configuration from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetFormat7ConfigurationPacket (fc2Context context, fc2Format7ImageSettings \*imageSettings, unsigned int packetSize)

Set the current Format7 configuration to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetFormat7Configuration (fc2Context context, fc2Format7ImageSettings \*imageSettings, float percentSpeed)

Set the current Format7 configuration to the camera.

# 6.11.1 Detailed Description

These functions deal with Format7 custom image control on the camera.

## 6.11.2 Function Documentation

6.11.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetFormat7Configuration ( fc2Context context, fc2Format7ImageSettings \* imageSettings, unsigned int \* packetSize, float \* percentage )

Get the current Format7 configuration from the camera.

This call will only succeed if the camera is already in Format7.

context	The fc2Context to be used.
image-	Current image settings.
Settings	
packetSize	Current packet size.
percentage	Current packet size as a percentage.

6.11 Format7 61

## Returns

A fc2Error indicating the success or failure of the function.

6.11.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetFormat7Info ( fc2Context context, fc2Format7Info \* info, BOOL \* pSupported )

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

The mode must be specified in the Format7Info structure in order for the function to succeed.

## **Parameters**

context	The fc2Context to be used.
info	Structure to be filled with the capabilities of the specified mode and the
	current state in the specified mode.
pSupported	Whether the specified mode is supported.

## **Returns**

A fc2Error indicating the success or failure of the function.

6.11.2.3 FLYCAPTURE2\_C\_API fc2Error fc2SetFormat7Configuration ( fc2Context context, fc2Format7ImageSettings \* imageSettings, float percentSpeed )

Set the current Format7 configuration to the camera.

# **Parameters**

context	The fc2Context to be used.
image-	Image settings to be written to the camera.
Settings	
percent-	Packet size as a percentage to be written to the camera.
Speed	

# Returns

A fc2Error indicating the success or failure of the function.

6.11.2.4 FLYCAPTURE2\_C\_API fc2Error fc2SetFormat7ConfigurationPacket ( fc2Context context, fc2Format7ImageSettings \* imageSettings, unsigned int packetSize )

Set the current Format7 configuration to the camera.

# **Parameters**

context	The fc2Context to be used.
image-	Image settings to be written to the camera.
Settings	
packetSize	Packet size to be written to the camera.

## Returns

A fc2Error indicating the success or failure of the function.

6.11.2.5 FLYCAPTURE2\_C\_API fc2Error fc2ValidateFormat7Settings ( fc2Context context, fc2Format7ImageSettings \* imageSettings, BOOL \* settingsAreValid, fc2Format7PacketInfo \* packetInfo )

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

The current image settings are cached while validation is taking place. The cached settings are restored when validation is complete.

## **Parameters**

context	The fc2Context to be used.
image-	Structure containing the image settings.
Settings	
settingsAre-	Whether the settings are valid.
Valid	
packetInfo	Packet size information that can be used to determine a valid packet
	size.

# Returns

A fc2Error indicating the success or failure of the function.

# 6.12 GVCP Register Operation

These functions deal with GVCP register operation on the camera.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegister (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register.

 FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register with broadcast.

FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPRegister (fc2Context context, unsigned int address, unsigned int \*pValue)

Read a GVCP register.

- FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegisterBlock (fc2Context context, unsigned int address, const unsigned int \*pBuffer, unsigned int length)
  - Write a GVCP register block.
- FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPRegisterBlock (fc2Context context, unsigned int address, unsigned int \*pBuffer, unsigned int length)

Read a GVCP register block.

• FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPMemory (fc2Context context, unsigned int address, const unsigned char \*pBuffer, unsigned int length)

Write a GVCP memory block.

FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPMemory (fc2Context context, unsigned int address, unsigned char \*pBuffer, unsigned int length)

Read a GVCP memory block.

# 6.12.1 Detailed Description

These functions deal with GVCP register operation on the camera.

# 6.12.2 Function Documentation

6.12.2.1 FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPMemory ( fc2Context context, unsigned int address, unsigned char \* pBuffer, unsigned int length )

Read a GVCP memory block.

context	The fc2Context to be used.
address	GVCP address to be read from.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

An Error indicating the success or failure of the function.

6.12.2.2 FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPRegister ( fc2Context context, unsigned int \* pValue )

Read a GVCP register.

## **Parameters**

context	The fc2Context to be used.
address	GVCP address to be read from.
pValue	The value that is read.

## Returns

An Error indicating the success or failure of the function.

6.12.2.3 FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPRegisterBlock ( fc2Context context, unsigned int \* pBuffer, unsigned int length )

Read a GVCP register block.

## **Parameters**

context	The fc2Context to be used.
address	GVCP address to be read from.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

## Returns

An Error indicating the success or failure of the function.

6.12.2.4 FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPMemory ( fc2Context context, unsigned int address, const unsigned char \* pBuffer, unsigned int length )

Write a GVCP memory block.

context	The fc2Context to be used.
address	GVCP address to be write to.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

An Error indicating the success or failure of the function.

6.12.2.5 FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegister ( fc2Context context, unsigned int address, unsigned int value )

Write a GVCP register.

## **Parameters**

	context	The fc2Context to be used.
ĺ	address	GVCP address to be written to.
	value	The value to be written.

## Returns

An Error indicating the success or failure of the function.

6.12.2.6 FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegisterBlock ( fc2Context context, unsigned int address, const unsigned int \* pBuffer, unsigned int length )

Write a GVCP register block.

## **Parameters**

context	The fc2Context to be used.
address	GVCP address to be write to.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

## **Returns**

An Error indicating the success or failure of the function.

6.12.2.7 FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegisterBroadcast ( fc2Context context, unsigned int address, unsigned int value )

Write a GVCP register with broadcast.

context	The fc2Context to be used.
address	GVCP address to be written to.
value	The value to be written.

An Error indicating the success or failure of the function.

# 6.13 GigE property manipulation

These functions deal with GigE properties.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEProperty (fc2Context context, fc2-GigEProperty \*pGigEProp)

Get the specified GigEProperty.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEProperty (fc2Context context, const fc2GigEProperty \*pGigEProp)

Set the specified GigEProperty.

FLYCAPTURE2\_C\_API fc2Error fc2DiscoverGigEPacketSize (fc2Context context, unsigned int \*packetSize)

Discover the largest packet size that works for the network link between the PC and the camera.

## 6.13.1 Detailed Description

These functions deal with GigE properties.

# 6.13.2 Function Documentation

6.13.2.1 FLYCAPTURE2\_C\_API fc2Error fc2DiscoverGigEPacketSize ( fc2Context context, unsigned int \* packetSize )

Discover the largest packet size that works for the network link between the PC and the camera.

This is useful in cases where there may be multiple links between the PC and the camera and there is a possibility of a component not supporting the recommended jumbo frame packet size of 9000.

## **Parameters**

context	The fc2Context to be used.
packetSize	The maximum packet size supported by the link.

# Returns

An Error indicating the success or failure of the function.

6.13.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEProperty ( fc2Context context, fc2GigEProperty \* pGigEProp )

Get the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

# **Parameters**

context	The fc2Context to be used.
pGigEProp	The GigE property to get.

# Returns

An Error indicating the success or failure of the function.

6.13.2.3 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEProperty ( fc2Context context, const fc2GigEProperty \* pGigEProp )

Set the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

## **Parameters**

context	The fc2Context to be used.
pGigEProp	The GigE property to set.

# Returns

An Error indicating the success or failure of the function.

# 6.14 GigE image settings

These functions deal with GigE image setting.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2QueryGigEImagingMode (fc2Context context, fc2Mode mode, BOOL \*isSupported)

Check if the particular imaging mode is supported by the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImagingMode (fc2Context context, fc2Mode \*mode)

Get the current imaging mode on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImagingMode (fc2Context context, fc2Mode mode)

Set the current imaging mode to the camera.

• FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageSettingsInfo (fc2Context context, fc2GigEImageSettingsInfo \*pInfo)

Get information about the image settings possible on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageSettings (fc2Context context, fc2GigEImageSettings \*pImageSettings)

Get the current image settings on the camera.

• FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImageSettings (fc2Context context, const fc2GigEImageSettings \*pImageSettings)

Set the image settings specified to the camera.

# 6.14.1 Detailed Description

These functions deal with GigE image setting.

# 6.14.2 Function Documentation

6.14.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageSettings ( fc2Context context, fc2GigEImageSettings \* plmageSettings )

Get the current image settings on the camera.

context	The fc2Context to be used.
plmage-	Current image settings on camera.
Settings	

An Error indicating the success or failure of the function.

# 6.14.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetGigElmageSettingsInfo ( fc2Context context, fc2GigElmageSettingsInfo \* plnfo )

Get information about the image settings possible on the camera.

## **Parameters**

context	The fc2Context to be used.
pInfo	Image settings information.

## Returns

An Error indicating the success or failure of the function.

# 6.14.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetGigElmagingMode ( fc2Context context, fc2Mode \* mode )

Get the current imaging mode on the camera.

## **Parameters**

context	The fc2Context to be used.
mode	Current imaging mode on the camera.

# Returns

An Error indicating the success or failure of the function.

# 6.14.2.4 FLYCAPTURE2\_C\_API fc2Error fc2QueryGigElmagingMode ( fc2Context context, fc2Mode mode, BOOL \* isSupported )

Check if the particular imaging mode is supported by the camera.

## **Parameters**

context	The fc2Context to be used.
mode	The mode to check.
isSupported	Whether the mode is supported.

## Returns

An Error indicating the success or failure of the function.

# 6.14.2.5 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImageSettings ( fc2Context context, const fc2GigEImageSettings \* plmageSettings )

Set the image settings specified to the camera.

## **Parameters**

context	The fc2Context to be used.
plmage-	Image settings to set to camera.
Settings	

## Returns

An Error indicating the success or failure of the function.

# 6.14.2.6 FLYCAPTURE2\_C\_API fc2Error fc2SetGigElmagingMode ( fc2Context context, fc2Mode mode )

Set the current imaging mode to the camera.

This should only be done when the camera is not streaming images.

# **Parameters**

	context	The fc2Context to be used.
Ī	mode	Imaging mode to set to the camera.

# Returns

An Error indicating the success or failure of the function.

# 6.15 GigE image binning settings

These functions deal with GigE image binning settings.

## **Functions**

- FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageBinningSettings (fc2Context context, unsigned int \*horzBinnningValue, unsigned int \*vertBinnningValue)

  Get the current binning settings on the camera.
- FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImageBinningSettings (fc2Context context, unsigned int horzBinnningValue, unsigned int vertBinnningValue)
   Set the specified binning values to the camera.

# 6.15.1 Detailed Description

These functions deal with GigE image binning settings.

## 6.15.2 Function Documentation

6.15.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageBinningSettings ( fc2Context context, unsigned int \* horzBinnningValue, unsigned int \* vertBinnningValue )

Get the current binning settings on the camera.

## **Parameters**

context	The fc2Context to be used.
horz-	Current horizontal binning value.
Binnning-	
Value	
vert-	Current vertical binning value.
Binnning-	
Value	

## Returns

An Error indicating the success or failure of the function.

6.15.2.2 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImageBinningSettings ( fc2Context context, unsigned int horzBinnningValue, unsigned int vertBinnningValue )

Set the specified binning values to the camera.

It is recommended that GetGigEImageSettingsInfo() be called after this function succeeds to retrieve the new image settings information for the new binning mode.

# **Parameters**

context	The fc2Context to be used.
horz-	Horizontal binning value.
Binnning-	
Value	
vert-	Vertical binning value.
Binnning-	
Value	

# Returns

An Error indicating the success or failure of the function.

# 6.16 GigE image stream configuration

These functions deal with GigE image stream configuration.

## **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2GetNumStreamChannels (fc2Context context, unsigned int \*numChannels)

Get the number of stream channels present on the camera.

• FLYCAPTURE2\_C\_API fc2Error fc2GetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel \*pChannel)

Get the stream channel information for the specified channel.

FLYCAPTURE2\_C\_API fc2Error fc2SetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel \*pChannel)

Set the stream channel information for the specified channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEConfig (fc2Context context, fc2Gig-EConfig \*pConfig)

Get the current gige config on the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEConfig (fc2Context context, const fc2GigEConfig \*pConfig)

Set the gige config specified to the camera.

# 6.16.1 Detailed Description

These functions deal with GigE image stream configuration.

# 6.16.2 Function Documentation

6.16.2.1 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEConfig ( fc2Context context, fc2GigEConfig \* pConfig )

Get the current gige config on the camera.

context	The fc2Context to be used.
pGigEConfig	Current configuration on camera.

An Error indicating the success or failure of the function.

6.16.2.2 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEStreamChannelInfo ( fc2Context context, unsigned int channel, fc2GigEStreamChannel \* pChannel )

Get the stream channel information for the specified channel.

## **Parameters**

	context	The fc2Context to be used.
Γ	channel	Channel number to use.
Γ	pChannel	Stream channel information for the specified channel.

## Returns

An Error indicating the success or failure of the function.

6.16.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetNumStreamChannels ( fc2Context context, unsigned int \* numChannels )

Get the number of stream channels present on the camera.

## **Parameters**

context	The fc2Context to be used.
num-	Number of stream channels present.
Channels	

## Returns

An Error indicating the success or failure of the function.

6.16.2.4 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEConfig ( fc2Context context, const fc2GigEConfig \* pConfig )

Set the gige config specified to the camera.

context	The fc2Context to be used.
pGigEConfig	configuration to set to camera.

An Error indicating the success or failure of the function.

6.16.2.5 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEStreamChannelInfo ( fc2Context context, unsigned int channel, fc2GigEStreamChannel \* pChannel )

Set the stream channel information for the specified channel.

Note that the source UDP port of the stream channel is read-only.

# **Parameters**

СО	ntext	The fc2Context to be used.
cha	annel	Channel number to use.
pCha	annel	Stream channel information to use for the specified channel.

# Returns

An Error indicating the success or failure of the function.

# 6.17 Image Operation

The Image operations are used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

## **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2SetDefaultColorProcessing (fc2Color-ProcessingAlgorithm defaultMethod)

Set the default color processing algorithm.

 FLYCAPTURE2\_C\_API fc2Error fc2GetDefaultColorProcessing (fc2Color-ProcessingAlgorithm \*pDefaultMethod)

Get the default color processing algorithm.

FLYCAPTURE2\_C\_API fc2Error fc2SetDefaultOutputFormat (fc2PixelFormat format)

Set the default output pixel format.

FLYCAPTURE2\_C\_API fc2Error fc2GetDefaultOutputFormat (fc2PixelFormat \*pFormat)

Get the default output pixel format.

FLYCAPTURE2\_C\_API fc2Error fc2DetermineBitsPerPixel (fc2PixelFormat format, unsigned int \*pBitsPerPixel)

Calculate the bits per pixel for the specified pixel format.

FLYCAPTURE2\_C\_API fc2Error fc2CreateImage (fc2Image \*pImage)
 Create a fc2Image.

• FLYCAPTURE2\_C\_API fc2Error fc2DestroyImage (fc2Image \*image)

Destroy the fc2Image.

FLYCAPTURE2\_C\_API fc2Error fc2SetImageDimensions (fc2Image \*pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageDimensions (fc2Image \*pImage, unsigned int \*pRows, unsigned int \*pCols, unsigned int \*pStride, fc2PixelFormat \*pPixelFormat, fc2BayerTileFormat \*pBayerFormat)

Get the image dimensions associated with the image object.

FLYCAPTURE2\_C\_API fc2Error fc2SetImageColorProcessing (fc2Image \*p-Image, fc2ColorProcessingAlgorithm colorProc)

Set the color processing algorithm.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageColorProcessing (fc2Image \*p-Image, fc2ColorProcessingAlgorithm \*pColorProc)

Get the current color processing algorithm.

 FLYCAPTURE2\_C\_API fc2Error fc2SetImageData (fc2Image \*pImage, const unsigned char \*pData, unsigned int dataSize)

Set the data of the Image object.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageData (fc2Image \*pImage, unsigned char \*\*ppData)

Get a pointer to the data associated with the image.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageMetadata (fc2Image \*pImage, fc2-ImageMetadata \*pImageMetaData)

Get the metadata associated with the image.

FLYCAPTURE2\_C\_API fc2TimeStamp fc2GetImageTimeStamp (fc2Image \*p-Image)

Get the timestamp data associated with the image.

 FLYCAPTURE2\_C\_API fc2Error fc2SaveImage (fc2Image \*pImage, const char \*pFilename, fc2ImageFileFormat format)

Save the image to the specified file name with the file format specified.

 FLYCAPTURE2\_C\_API fc2Error fc2SaveImageWithOption (fc2Image \*pImage, const char \*pFilename, fc2ImageFileFormat format, void \*pOption)

Save the image to the specified file name with the file format specified.

- FLYCAPTURE2\_C\_API fc2Error fc2ConvertImage (fc2Image \*pImageIn, fc2-Image \*pImageOut)
- FLYCAPTURE2\_C\_API fc2Error fc2ConvertImageTo (fc2PixelFormat format, fc2Image \*pImageIn, fc2Image \*pImageOut)

Converts the current image buffer to the specified output format and stores the result in the specified image.

• FLYCAPTURE2\_C\_API fc2Error fc2CalculateImageStatistics (fc2Image \*p-Image, fc2ImageStatisticsContext \*pImageStatisticsContext)

Calculate statistics associated with the image.

## 6.17.1 Detailed Description

The Image operations are used to retrieve images from a camera, convert between multiple pixel formats and save images to disk. Operations on images are not guaranteed to be thread safe. It is recommended that operations on images be protected by thread synchronization constructs such as mutexes.

## 6.17.2 Function Documentation

6.17.2.1 FLYCAPTURE2\_C\_API fc2Error fc2CalculateImageStatistics ( fc2Image \* pImage, fc2ImageStatisticsContext \* pImageStatisticsContext )

Calculate statistics associated with the image.

In order to collect statistics for a particular channel, the enabled flag for the channel must be set to true. Statistics can only be collected for images in Mono8, Mono16, RGB, RGBU, BGR and BGRU.

plmage	The fc2Image to be used.
plmage-	The fc2ImageStatisticsContext to hold the statistics.
Statistics-	
Context	

A fc2Error indicating the success or failure of the function.

# 6.17.2.2 FLYCAPTURE2\_C\_API fc2Error fc2ConvertImage ( fc2Image \* plmageIn, fc2Image \* plmageOut )

## **Parameters**

pli	mageIn	
plma	ageOut	

## Returns

A fc2Error indicating the success or failure of the function.

6.17.2.3 FLYCAPTURE2\_C\_API fc2Error fc2ConvertImageTo ( fc2PixelFormat format, fc2Image \* plmageOut )

Converts the current image buffer to the specified output format and stores the result in the specified image.

The destination image does not need to be configured in any way before the call is made.

## **Parameters**

format	Output format of the converted image.
plmageln	Input image.
plmageOut	Output image.

## Returns

A fc2Error indicating the success or failure of the function.

# 6.17.2.4 FLYCAPTURE2\_C\_API fc2Error fc2CreateImage ( fc2Image \* pImage )

# Create a fc2Image.

If externally allocated memory is to be used for the converted image, simply assigning the pData member of the fc2Image structure is insufficient. fc2SetImageData() should be called in order to populate the fc2Image structure correctly.

## See also

fc2SetImageData()

## **Parameters**

plmage	Pointer to image to be created.

## Returns

A fc2Error indicating the success or failure of the function.

6.17.2.5 FLYCAPTURE2\_C\_API fc2Error fc2DestroyImage ( fc2Image \* image )

Destroy the fc2Image.

## **Parameters**

image	Pointer to image to be destroyed.

## Returns

A fc2Error indicating the success or failure of the function.

6.17.2.6 FLYCAPTURE2\_C\_API fc2Error fc2DetermineBitsPerPixel ( fc2PixelFormat format, unsigned int \* pBitsPerPixel )

Calculate the bits per pixel for the specified pixel format.

# **Parameters**

format	The pixel format.
pBitsPer-	The bits per pixel.
Pixel	

# Returns

A fc2Error indicating the success or failure of the function.

6.17.2.7 FLYCAPTURE2\_C\_API fc2Error fc2GetDefaultColorProcessing ( fc2ColorProcessingAlgorithm \* pDefaultMethod )

Get the default color processing algorithm.

pDefault-	The default color processing algorithm.
Method	

A fc2Error indicating the success or failure of the function.

6.17.2.8 FLYCAPTURE2\_C\_API fc2Error fc2GetDefaultOutputFormat ( fc2PixelFormat \* pFormat )

Get the default output pixel format.

#### **Parameters**

pFormat	The default pixel format.

# Returns

A fc2Error indicating the success or failure of the function.

6.17.2.9 FLYCAPTURE2\_C\_API fc2Error fc2GetImageColorProcessing ( fc2Image \* pImage, fc2ColorProcessingAlgorithm \* pColorProc )

Get the current color processing algorithm.

# **Parameters**

plmage	The fc2Image to be used.

## See also

fc2SetColorProcessing()

# Returns

The current color processing algorithm.

6.17.2.10 FLYCAPTURE2\_C\_API fc2Error fc2GetImageData ( fc2Image \* pImage, unsigned char \*\* ppData )

Get a pointer to the data associated with the image.

This function is considered unsafe. The pointer returned could be invalidated if the buffer is resized or released. The pointer may also be invalidated if the Image object is passed to fc2RetrieveBuffer().

plmage	The fc2Image to be used.
ppData	A pointer to the image data.

A fc2Error indicating the success or failure of the function.

6.17.2.11 FLYCAPTURE2\_C\_API fc2Error fc2GetImageDimensions ( fc2Image \* pImage, unsigned int \* pRows, unsigned int \* pCols, unsigned int \* pStride, fc2PixelFormat \* pPixelFormat, fc2BayerTileFormat \* pBayerFormat )

Get the image dimensions associated with the image object.

## **Parameters**

plmage	The fc2Image to be used.
pRows	Number of rows.
pCols	Number of columns.
pStride	The stride.
pPixel-	Pixel format.
Format	
pBayer-	Bayer tile format.
Format	

6.17.2.12 FLYCAPTURE2\_C\_API fc2Error fc2GetImageMetadata ( fc2Image \* pImage, fc2ImageMetadata \* pImageMetaData )

Get the metadata associated with the image.

This includes embedded image information.

## **Parameters**

plmage The fc2Image to be used.
---------------------------------

## Returns

Metadata associated with the image.

6.17.2.13 FLYCAPTURE2\_C\_API fc2TimeStamp fc2GetImageTimeStamp ( fc2Image \* pImage )

Get the timestamp data associated with the image.

plmage	The fc2Image to be used.

Timestamp data associated with the image.

6.17.2.14 FLYCAPTURE2\_C\_API fc2Error fc2SaveImage ( fc2Image \* pImage, const char \* pFilename, fc2ImageFileFormat format )

Save the image to the specified file name with the file format specified.

#### **Parameters**

plmage	The fc2Image to be used.
pFilename	Filename to save image with.
format	File format to save in.

#### **Returns**

A fc2Error indicating the success or failure of the function.

6.17.2.15 FLYCAPTURE2\_C\_API fc2Error fc2SaveImageWithOption ( fc2Image \* pImage, const char \* pFilename, fc2ImageFileFormat format, void \* pOption )

Save the image to the specified file name with the file format specified.

#### **Parameters**

	plmage	The fc2lmage to be used.
	pFilename	Filename to save image with.
	format	File format to save in.
Γ	pOption	Options for saving image.

# Returns

A fc2Error indicating the success or failure of the function.

6.17.2.16 FLYCAPTURE2\_C\_API fc2Error fc2SetDefaultColorProcessing ( fc2ColorProcessingAlgorithm defaultMethod )

Set the default color processing algorithm.

This method will be used for any image with the DEFAULT algorithm set. The method used is determined at the time of the Convert() call, therefore the most recent execution of this function will take precedence. The default setting is shared within the current process.

#### **Parameters**

default-	The color processing algorithm to set.
Method	

## Returns

A fc2Error indicating the success or failure of the function.

# 6.17.2.17 FLYCAPTURE2\_C\_API fc2Error fc2SetDefaultOutputFormat ( fc2PixelFormat format )

Set the default output pixel format.

This format will be used for any call to Convert() that does not specify an output format. The format used will be determined at the time of the Convert() call, therefore the most recent execution of this function will take precedence. The default is shared within the current process.

## **Parameters**

format	The output pixel format to set.
--------	---------------------------------

#### Returns

A fc2Error indicating the success or failure of the function.

# 6.17.2.18 FLYCAPTURE2\_C\_API fc2Error fc2SetImageColorProcessing ( fc2Image \* pImage, fc2ColorProcessingAlgorithm colorProc )

Set the color processing algorithm.

This should be set on the input image object.

## **Parameters**

plmage	The fc2Image to be used.
colorProc	The color processing algorithm to use.

#### See also

fc2GetColorProcessing()

#### Returns

An Error indicating the success or failure of the function.

6.17.2.19 FLYCAPTURE2\_C\_API fc2Error fc2SetImageData ( fc2Image \* pImage, const unsigned char \* pData, unsigned int dataSize )

Set the data of the Image object.

Ownership of the image buffer is not transferred to the Image object. It is the user's responsibility to delete the buffer when it is no longer in use.

#### **Parameters**

р	lmage	The fc2Image to be used.
	pData	Pointer to the image buffer.
da	taSize	Size of the image buffer.

#### **Returns**

A fc2Error indicating the success or failure of the function.

6.17.2.20 FLYCAPTURE2\_C\_API fc2Error fc2SetImageDimensions ( fc2Image \* pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

## **Parameters**

plmage	The fc2Image to be used.
rows	Number of rows to set.
cols	Number of cols to set.
stride	Stride to set.
pixelFormat	Pixel format to set.
bayerFormat	Bayer tile format to set.

# Returns

A fc2Error indicating the success or failure of the function.

# 6.18 Image Statistics Operation

The Image Statistics operation provides the functionality for the user to collect image channel statistics.

#### **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2CreateImageStatistics (fc2ImageStatistics-Context \*pImageStatisticsContext)

Create a statistics context.

 FLYCAPTURE2\_C\_API fc2Error fc2DestroyImageStatistics (fc2ImageStatistics-Context imageStatisticsContext)

Destroy a statistics context.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableAll (fc2Image-StatisticsContext imageStatisticsContext)

Enable all channels.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsDisableAll (fc2Image-StatisticsContext imageStatisticsContext)

Disable all channels.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableGreyOnly (fc2Image-StatisticsContext imageStatisticsContext)

Enable only the grey channel.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableRGBOnly (fc2Image-StatisticsContext imageStatisticsContext)

Enable only the RGB channels.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableHSLOnly (fc2Image-StatisticsContext imageStatisticsContext)

Enable only the HSL channels.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelStatus (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, BOOL \*p-Enabled)

Get the status of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2SetChannelStatus (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled)

Set the status of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelRange (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*pMin, unsigned int \*pMax)

Get the range of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelPixelValueRange (fc2Image-StatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*pPixelValueMin, unsigned int \*pPixelValueMax)

Get the range of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelNumPixelValues (fc2Image-StatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*pNumPixelValues) Get the number of unique pixel values in the image.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelMean (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, float \*pPixel-ValueMean)

Get the mean of the image.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelHistogram (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, int \*\*pp-Histogram)

Get the histogram for the image.

 FLYCAPTURE2\_C\_API fc2Error fc2GetImageStatistics (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*p-RangeMin, unsigned int \*pRangeMax, unsigned int \*pPixelValueMin, unsigned int \*pPixelValueMax, unsigned int \*pNumPixelValues, float \*pPixelValueMean, int \*\*ppHistogram)

Get all statistics for the image.

# 6.18.1 Detailed Description

The Image Statistics operation provides the functionality for the user to collect image channel statistics.

## 6.18.2 Function Documentation

6.18.2.1 FLYCAPTURE2\_C\_API fc2Error fc2CreateImageStatistics ( fc2ImageStatisticsContext \* plmageStatisticsContext )

Create a statistics context.

## **Parameters**

plmage-	A statistics context.
Statistics-	
Context	

#### **Returns**

A fc2Error indicating the success or failure of the function.

# 6.18.2.2 FLYCAPTURE2\_C\_API fc2Error fc2DestroyImageStatistics ( fc2ImageStatisticsContext imageStatisticsContext)

Destroy a statistics context.

image-	A statistics context.
Statistics-	
Context	Any 2 2010 10:00:05 for EliConture C. by Dovision

A fc2Error indicating the success or failure of the function.

6.18.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelHistogram (
fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel
channel, int \*\* ppHistogram )

Get the histogram for the image.

## **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
ppHistogram	Pointer to an array containing the histogram.

#### Returns

An Error indicating the success or failure of the function.

6.18.2.4 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelMean ( fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, float \* pPixelValueMean )

Get the mean of the image.

## **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
pPixelValue-	The mean of the image.
Mean	

# Returns

An Error indicating the success or failure of the function.

6.18.2.5 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelNumPixelValues (
fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel
channel, unsigned int \* pNumPixelValues )

Get the number of unique pixel values in the image.

#### **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
pNumPixel-	The number of unique pixel values.
Values	

## Returns

An Error indicating the success or failure of the function.

6.18.2.6 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelPixelValueRange (
fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel
channel, unsigned int \* pPixelValueMin, unsigned int \* pPixelValueMax )

Get the range of a statistics channel.

The values returned are the maximum values recorded for all pixels in the image.

## **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
pPixelValue-	The minimum pixel value.
Min	
pPixelValue-	The maximum pixel value.
Max	

## Returns

An Error indicating the success or failure of the function.

6.18.2.7 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelRange ( fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \* pMin, unsigned int \* pMax )

Get the range of a statistics channel.

The values returned are the maximum possible values for any given pixel in the image. This is generally 0-255 for 8 bit images, and 0-65535 for 16 bit images.

## **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
pMin	The minimum possible value.
рМах	The maximum possible value.

# Returns

An Error indicating the success or failure of the function.

6.18.2.8 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelStatus ( fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, BOOL \* pEnabled )

Get the status of a statistics channel.

#### See also

fc2SetChannelStatus()

## **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
pEnabled	Whether the channel is enabled.

# Returns

An Error indicating the success or failure of the function.

6.18.2.9 FLYCAPTURE2\_C\_API fc2Error fc2GetImageStatistics ( fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \* pRangeMin, unsigned int \* pRangeMax, unsigned int \* pPixelValueMin, unsigned int \* pPixelValueMax, unsigned int \* pNumPixelValues, float \* pPixelValueMean, int \*\* ppHistogram )

Get all statistics for the image.

image-	The statistics context.
Statistics-	
Context	

channel	The statistics channel.
pRangeMin	The minimum possible value.
pRangeMax	The maximum possible value.
pPixelValue-	The minimum pixel value.
Min	
pPixelValue-	The maximum pixel value.
Max	
pNumPixel-	The number of unique pixel values.
Values	
pPixelValue-	The mean of the image.
Mean	
ppHistogram	Pointer to an array containing the histogram.

A fc2Error indicating the success or failure of the function.

# 6.18.2.10 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsDisableAll ( fc2ImageStatisticsContext imageStatisticsContext )

Disable all channels.

## **Parameters**

image-	A statistics context.
Statistics-	
Context	

# Returns

An Error indicating the success or failure of the function.

# 6.18.2.11 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableAll ( fc2ImageStatisticsContext imageStatisticsContext )

Enable all channels.

image-	A statistics context.
Statistics-	
Context	

An Error indicating the success or failure of the function.

# 6.18.2.12 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableGreyOnly ( fc2ImageStatisticsContext imageStatisticsContext )

Enable only the grey channel.

#### **Parameters**

image-	A statistics context.
Statistics-	
Context	

## Returns

An Error indicating the success or failure of the function.

# 6.18.2.13 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableHSLOnly ( fc2ImageStatisticsContext imageStatisticsContext )

Enable only the HSL channels.

## **Parameters**

image-	A statistics context.
Statistics-	
Context	

# Returns

An Error indicating the success or failure of the function.

# 6.18.2.14 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableRGBOnly ( fc2ImageStatisticsContext imageStatisticsContext )

Enable only the RGB channels.

image-	A statistics context.
Statistics-	
Context	

An Error indicating the success or failure of the function.

```
6.18.2.15 FLYCAPTURE2_C_API fc2Error fc2SetChannelStatus ( fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled )
```

Set the status of a statistics channel.

#### See also

fc2GetChannelStatus()

## **Parameters**

image-	A statistics context.
Statistics-	
Context	
channel	The statistics channel.
enabled	Whether the channel should be enabled.

## Returns

An Error indicating the success or failure of the function.

# 6.19 TopologyNode Operation

The TopologyNode operation provides the functionality for the user to generate a tree structure of all cameras and devices connected to a computer.

#### **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2CreateTopologyNode (fc2TopologyNode-Context \*pTopologyNodeContext)

Create a TopologyNode context.

 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetGuid (fc2TopologyNode-Context TopologyNodeContext, fc2PGRGuid \*pGuid)

Get the PGRGuid associated with the node.

 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetDeviceId (fc2Topology-NodeContext TopologyNodeContext, int \*pID)

Get the device ID associated with the node.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNodeType (fc2Topology-NodeContext TopologyNodeContext, fc2NodeType \*pNodeType)

Get the node type associated with the node.

 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetInterfaceType (fc2-TopologyNodeContext TopologyNodeContext, fc2InterfaceType \*pInterface-Type)

Get the interface type associated with the node.

- FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumChildren (fc2-TopologyNodeContext TopologyNodeContext, unsigned int \*pNumChildNodes)
   Get the number of child nodes.
- FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetChild (fc2TopologyNodeContext TopologyNodeContext, unsigned int position, fc2TopologyNodeContext \*pChildTopologyNodeContext)

Get child node located at the specified position.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeAddChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeChild-Context)

Add the specified TopologyNode as a child of the node.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumPorts (fc2Topology-NodeContext TopologyNodeContext, unsigned int \*pNumPorts)

Get the number of ports.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetPortType (fc2Topology-NodeContext TopologyNodeContext, unsigned int position, fc2PortType \*pPortType)

Get type of port located at the specified position.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeAddPortType (fc2Topology-NodeContext TopologyNodeContext, fc2PortType portType)

Add the specified PortType as a port of the node.

- FLYCAPTURE2\_C\_API BOOL fc2TopologyNodeAssignGuidToNode (fc2TopologyNodeContext TopologyNodeContext, fc2PGRGuid guid, int deviceId)
   Assign a PGRGuid and device ID to the node.
- FLYCAPTURE2\_C\_API BOOL fc2TopologyNodeAssignGuidToNodeEx (fc2-TopologyNodeContext TopologyNodeContext, fc2PGRGuid guid, int deviceId, fc2NodeType nodeType)

Assign a PGRGuid, device ID and nodeType to the node.

 FLYCAPTURE2\_C\_API fc2Error fc2DestroyTopologyNode (fc2TopologyNode-Context TopologyNodeContext)

Destroy a TopologyNode context.

# 6.19.1 Detailed Description

The TopologyNode operation provides the functionality for the user to generate a tree structure of all cameras and devices connected to a computer.

## 6.19.2 Function Documentation

6.19.2.1 FLYCAPTURE2\_C\_API fc2Error fc2CreateTopologyNode ( fc2TopologyNodeContext \* pTopologyNodeContext )

Create a TopologyNode context.

# **Parameters**

pTopology-	A Topology Node context.
Node-	
Context	

#### **Returns**

A fc2Error indicating the success or failure of the function.

6.19.2.2 FLYCAPTURE2\_C\_API fc2Error fc2DestroyTopologyNode ( fc2TopologyNodeContext TopologyNodeContext )

Destroy a TopologyNode context.

Topology-	A Topology Node context.
Node-	
Context	

A fc2Error indicating the success or failure of the function.

6.19.2.3 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeAddChild (
fc2TopologyNodeContext TopologyNodeContext, fc2TopologyNodeContext
TopologyNodeChildContext)

Add the specified TopologyNode as a child of the node.

#### **Parameters**

ſ	Topology-	The Topology Node context to use.
	Node-	
	Context	
Γ	Topology-	The TopologyNode child context to add.
	NodeChild-	
	Context	

#### Returns

A fc2Error indicating the success or failure of the function.

6.19.2.4 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeAddPortType (
fc2TopologyNodeContext TopologyNodeContext, fc2PortType portType )

Add the specified PortType as a port of the node.

## **Parameters**

Topology	The Topology Node context to use.
	The Topology Node Context to use.
Node-	
Context	
portType	childPort The port to add.

# Returns

A fc2Error indicating the success or failure of the function.

6.19.2.5 FLYCAPTURE2\_C\_API BOOL fc2TopologyNodeAssignGuidToNode (
fc2TopologyNodeContext TopologyNodeContext, fc2PGRGuid guid, int
deviceId )

Assign a PGRGuid and device ID to the node.

# **Parameters**

Topology-	The Topology Node context to use.
Node-	
Context	
guid	PGRGuid to be assigned.
deviceId	Device ID to be assigned.

#### Returns

A fc2Error indicating the success or failure of the function.

6.19.2.6 FLYCAPTURE2\_C\_API BOOL fc2TopologyNodeAssignGuidToNodeEx (
fc2TopologyNodeContext TopologyNodeContext, fc2PGRGuid guid, int
deviceId, fc2NodeType nodeType )

Assign a PGRGuid, device ID and nodeType to the node.

#### **Parameters**

Topology- Node-	The Topology Node context to use.
Context	
guid	PGRGuid to be assigned.
deviceld	Device ID to be assigned.
nodeType	NodeType to be assigned

#### Returns

A fc2Error indicating the success or failure of the function.

6.19.2.7 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetChild (
fc2TopologyNodeContext TopologyNodeContext, unsigned int position,
fc2TopologyNodeContext \* pChildTopologyNodeContext )

Get child node located at the specified position.

Topology-	The Topology Node context to use.
Node-	
Context	
position	Position of the child node.
pChild-	The Topology Node context the contains information on the child topol-
Topology-	
Node-	
Context	

A fc2Error indicating the success or failure of the function.

6.19.2.8 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetDeviceld ( fc2TopologyNodeContext TopologyNodeContext, int \* pID )

Get the device ID associated with the node.

#### **Parameters**

Topology-	The Topology Node context to use.
Node-	
Context	
pID	Device ID of the node.

#### Returns

A fc2Error indicating the success or failure of the function.

6.19.2.9 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetGuid (
fc2TopologyNodeContext TopologyNodeContext, fc2PGRGuid \* pGuid )

Get the PGRGuid associated with the node.

# Parameters

Topology-	The Topology Node context to use.
Node-	
Context	
pGuid	The unique identifier associated with the node.

#### Returns

A fc2Error indicating the success or failure of the function.

6.19.2.10 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetInterfaceType (
fc2TopologyNodeContext TopologyNodeContext, fc2InterfaceType \*
pInterfaceType )

Get the interface type associated with the node.

Topology-	The Topology Node context to use.
Node-	
Context	

pInterface-	Interface type of the node.
Туре	

A fc2Error indicating the success or failure of the function.

```
6.19.2.11 FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetNodeType (
fc2TopologyNodeContext TopologyNodeContext, fc2NodeType * pNodeType
)
```

Get the node type associated with the node.

# **Parameters**

Topology-	The Topology Node context to use.
Node-	
Context	
pNodeType	Node type of the node.

# Returns

A fc2Error indicating the success or failure of the function.

6.19.2.12 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumChildren (
fc2TopologyNodeContext TopologyNodeContext, unsigned int \*
pNumChildNodes )

Get the number of child nodes.

Topology-	The Topology Node context to use.
Node-	
Context	
pNumChild-	Number of child nodes.
Nodes	

A fc2Error indicating the success or failure of the function.

6.19.2.13 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumPorts ( fc2TopologyNodeContext TopologyNodeContext, unsigned int \* pNumPorts )

Get the number of ports.

## **Parameters**

Topology-	The Topology Node context to use.
Node-	
Context	
pNumPorts	Number of ports.

## Returns

A fc2Error indicating the success or failure of the function.

6.19.2.14 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetPortType (
fc2TopologyNodeContext TopologyNodeContext, unsigned int position,
fc2PortType \* pPortType )

Get type of port located at the specified position.

#### **Parameters**

Topology-	The Topology Node context to use.
Node-	
Context	
position	Position of the port.
pPortType	PortType at the specified position.

# Returns

A fc2Error indicating the success or failure of the function.

6.20 Utilities 101

# 6.20 Utilities

The utility operations are used to query for general system information such as operating system, available memory etc.

#### **Functions**

- FLYCAPTURE2\_C\_API fc2Error fc2CheckDriver (const fc2PGRGuid \*pGuid)

  Check for driver compatibility for the given camera guid.
- FLYCAPTURE2\_C\_API fc2Error fc2GetDriverDeviceName (const fc2PGRGuid \*pGuid, char \*pDeviceName, size t \*deviceNameLength)

Get the driver's name for a device.

FLYCAPTURE2\_C\_API fc2Error fc2GetSystemInfo (fc2SystemInfo \*pSystemInfo)

Get system information.

- FLYCAPTURE2\_C\_API fc2Error fc2GetLibraryVersion (fc2Version \*pVersion)
   Get library version.
- FLYCAPTURE2\_C\_API fc2Error fc2LaunchBrowser (const char \*pAddress)

  Launch a URL in the system default browser.
- FLYCAPTURE2\_C\_API fc2Error fc2LaunchHelp (const char \*pFileName)

  Open a CHM file in the system default CHM viewer.
- FLYCAPTURE2\_C\_API fc2Error fc2LaunchCommand (const char \*p-Command)

Execute a command in the terminal.

 FLYCAPTURE2\_C\_API fc2Error fc2LaunchCommandAsync (const char \*p-Command, fc2AsyncCommandCallback pCallback, void \*pUserData)

Execute a command in the terminal.

• FLYCAPTURE2\_C\_API const char \* fc2ErrorToDescription (fc2Error error)

Get a string representation of an error.

## 6.20.1 Detailed Description

The utility operations are used to query for general system information such as operating system, available memory etc. It can also be used to launch browsers, CHM viewers or terminal commands.

# 6.20.2 Function Documentation

6.20.2.1 FLYCAPTURE2\_C\_API fc2Error fc2CheckDriver ( const fc2PGRGuid \* pGuid )

Check for driver compatibility for the given camera guid.

#### **Parameters**

pGuid The PGRGuid of the device to check.

FC2\_ERROR\_OK if the library is compatible with the currently loaded driver, otherwise an error indicating the type of failure.

6.20.2.2 FLYCAPTURE2\_C\_API const char\* fc2ErrorToDescription ( fc2Error error )

Get a string representation of an error.

#### **Parameters**

error	Error to be parsed.
-------	---------------------

# Returns

A fc2Error indicating the success or failure of the function.

6.20.2.3 FLYCAPTURE2\_C\_API fc2Error fc2GetDriverDeviceName ( const fc2PGRGuid \* pGuid, char \* pDeviceName, size\_t \* deviceNameLength )

Get the driver's name for a device.

## **Parameters**

pGuid	The PGRGuid of the device to check.
pDevice-	The device name will be returned in this string
Name	
pDevice-	The length of the device name string returned
NameLength	

## Returns

An Error indicating the success or failure of the function.

6.20.2.4 FLYCAPTURE2\_C\_API fc2Error fc2GetLibraryVersion ( fc2Version \* pVersion )

Get library version.

## **Parameters**

pVersion	Structure to receive the library version.

#### Returns

A fc2Error indicating the success or failure of the function.

6.20 Utilities 103

6.20.2.5 FLYCAPTURE2\_C\_API fc2Error fc2GetSystemInfo ( fc2SystemInfo \* pSystemInfo )

Get system information.

## **Parameters**

pSystemInfo	Structure to receive system information.

#### Returns

A fc2Error indicating the success or failure of the function.

6.20.2.6 FLYCAPTURE2\_C\_API fc2Error fc2LaunchBrowser ( const char \* pAddress )

Launch a URL in the system default browser.

#### **Parameters**

pAddress	URL to open in browser.
----------	-------------------------

#### Returns

A fc2Error indicating the success or failure of the function.

6.20.2.7 FLYCAPTURE2\_C\_API fc2Error fc2LaunchCommand ( const char \* pCommand )

Execute a command in the terminal.

This is a blocking call that will return when the command completes.

# **Parameters**

pCommand   Command to execute.
--------------------------------

## Returns

A fc2Error indicating the success or failure of the function.

6.20.2.8 FLYCAPTURE2\_C\_API fc2Error fc2LaunchCommandAsync ( const char \* pCommand, fc2AsyncCommandCallback, void \* pUserData )

Execute a command in the terminal.

This is a non-blocking call that will return immediately. The return value of the command can be retrieved in the callback.

# **Parameters**

pCommand	Command to execute.
pCallback	Callback to fire when command is complete.
pUserData	Data pointer to pass to callback.

# Returns

A fc2Error indicating the success or failure of the function.

6.20.2.9 FLYCAPTURE2\_C\_API fc2Error fc2LaunchHelp ( const char \* pFileName )

Open a CHM file in the system default CHM viewer.

# **Parameters**

pFileName	Filename of CHM file to open.

## Returns

A fc2Error indicating the success or failure of the function.

6.21 TypeDefs 105

# 6.21 TypeDefs

# **Data Structures**

struct fc2PGRGuid

A GUID to the camera.

# **Defines**

- #define FALSE 0
- #define TRUE 1
- #define FULL\_32BIT\_VALUE 0x7FFFFFF
- #define MAX\_STRING\_LENGTH 512

# **Typedefs**

- typedef int BOOL
- typedef void \* fc2Context

A context to the FlyCapture2 C library.

typedef void \* fc2GuiContext

A context to the FlyCapture2 C GUI library.

• typedef void \* fc2lmagelmpl

An internal pointer used in the fc2lmage structure.

• typedef void \* fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

• typedef void \* fc2TopologyNodeContext

A context referring to the TopologyNode object.

• typedef void \* fc2VideoContext

A context referring to the video recorder object.

# 6.21.1 Define Documentation

- 6.21.1.1 #define FALSE 0
- 6.21.1.2 #define FULL\_32BIT\_VALUE 0x7FFFFFF
- 6.21.1.3 #define MAX\_STRING\_LENGTH 512
- 6.21.1.4 #define TRUE 1
- 6.21.2 Typedef Documentation
- 6.21.2.1 typedef int BOOL

6.21.2.2 typedef void\* fc2Context

A context to the FlyCapture2 C library.

It must be created before performing any calls to the library.

6.21.2.3 typedef void\* fc2GuiContext

A context to the FlyCapture2 C GUI library.

It must be created before performing any calls to the library.

6.21.2.4 typedef void\* fc2ImageImpI

An internal pointer used in the fc2Image structure.

6.21.2.5 typedef void\* fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

6.21.2.6 typedef void\* fc2TopologyNodeContext

A context referring to the TopologyNode object.

6.21.2.7 typedef void\* fc2VideoContext

A context referring to the video recorder object.

6.22 Enumerations 107

## 6.22 Enumerations

#### **Enumerations**

• enum fc2Error { FC2\_ERROR\_UNDEFINED = -1, FC2\_ERROR\_OK, FC2-\_ERROR\_FAILED, FC2\_ERROR\_NOT\_IMPLEMENTED, FC2\_ERROR\_FAIL-ED\_BUS\_MASTER\_CONNECTION, FC2\_ERROR\_NOT\_CONNECTED, FC2-\_ERROR\_INIT\_FAILED, FC2\_ERROR\_NOT\_INTITIALIZED, FC2\_ERROR\_I-NVALID\_PARAMETER, FC2\_ERROR\_INVALID\_SETTINGS, FC2\_ERROR\_-INVALID BUS MANAGER, FC2 ERROR MEMORY ALLOCATION FAILED, FC2 ERROR LOW LEVEL FAILURE, FC2 ERROR NOT FOUND, FC2 -ERROR FAILED GUID, FC2 ERROR INVALID PACKET SIZE, FC2 ERR-OR\_INVALID\_MODE, FC2\_ERROR\_NOT\_IN\_FORMAT7, FC2\_ERROR\_NO-T\_SUPPORTED, FC2\_ERROR\_TIMEOUT, FC2\_ERROR\_BUS\_MASTER\_F-AILED, FC2 ERROR INVALID GENERATION, FC2 ERROR LUT FAILED, FC2 ERROR IIDC FAILED, FC2 ERROR STROBE FAILED, FC2 ERRO-R\_TRIGGER\_FAILED, FC2\_ERROR\_PROPERTY\_FAILED, FC2\_ERROR\_P-ROPERTY\_NOT\_PRESENT, FC2\_ERROR\_REGISTER\_FAILED, FC2\_ERR-OR READ REGISTER FAILED, FC2 ERROR WRITE REGISTER FAILED, FC2 ERROR ISOCH FAILED, FC2 ERROR ISOCH ALREADY STARTED, FC2 ERROR ISOCH NOT STARTED, FC2 ERROR ISOCH START FAIL-ED, FC2 ERROR ISOCH RETRIEVE BUFFER FAILED, FC2 ERROR ISO-CH STOP FAILED, FC2 ERROR ISOCH SYNC FAILED, FC2 ERROR IS-OCH\_BANDWIDTH\_EXCEEDED, FC2\_ERROR\_IMAGE\_CONVERSION\_FAI-LED, FC2\_ERROR\_IMAGE\_LIBRARY\_FAILURE, FC2\_ERROR\_BUFFER\_T-OO\_SMALL, FC2\_ERROR\_IMAGE\_CONSISTENCY\_ERROR, FC2\_ERROR-INCOMPATIBLE DRIVER, FC2 ERROR FORCE 32BITS = FULL 32BIT V-ALUE }

The error types returned by functions.

 enum fc2BusCallbackType { FC2\_BUS\_RESET, FC2\_ARRIVAL, FC2\_REMO-VAL, FC2\_CALLBACK\_TYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

The type of bus callback to register a callback function for.

enum fc2GrabMode { FC2\_DROP\_FRAMES, FC2\_BUFFER\_FRAMES, FC2\_UNSPECIFIED\_GRAB\_MODE, FC2\_GRAB\_MODE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

The grab strategy employed during image transfer.

enum fc2GrabTimeout { FC2\_TIMEOUT\_NONE = 0, FC2\_TIMEOUT\_INFINITE = -1, FC2\_TIMEOUT\_UNSPECIFIED = -2, FC2\_GRAB\_TIMEOUT\_FORCE\_-32BITS = FULL\_32BIT\_VALUE }

Timeout options for grabbing images.

 enum fc2BandwidthAllocation { FC2\_BANDWIDTH\_ALLOCATION\_OFF = 0, FC2\_BANDWIDTH\_ALLOCATION\_ON = 1, FC2\_BANDWIDTH\_ALLOCATION\_UNSUPPORTED = 2, FC2\_BANDWIDTH\_ALLOCATION\_UNSPECIFIED = 3, FC2\_BANDWIDTH\_ALLOCATION\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Bandwidth allocation options for 1394 devices.

enum fc2InterfaceType { FC2\_INTERFACE\_IEEE1394, FC2\_INTERFACE\_US-B\_2, FC2\_INTERFACE\_USB\_3, FC2\_INTERFACE\_GIGE, FC2\_INTERFACE\_UNKNOWN, FC2\_INTERFACE\_TYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Interfaces that a camera may use to communicate with a host.

enum fc2PropertyType { FC2\_BRIGHTNESS, FC2\_AUTO\_EXPOSURE, FC2\_SHARPNESS, FC2\_WHITE\_BALANCE, FC2\_HUE, FC2\_SATURATION, F-C2\_GAMMA, FC2\_IRIS, FC2\_FOCUS, FC2\_ZOOM, FC2\_PAN, FC2\_TILT, FC2\_SHUTTER, FC2\_GAIN, FC2\_TRIGGER\_MODE, FC2\_TRIGGER\_DELA-Y, FC2\_FRAME\_RATE, FC2\_TEMPERATURE, FC2\_UNSPECIFIED\_PROPERTY\_TYPE, FC2\_PROPERTY\_TYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE

#### Camera properties.

enum fc2FrameRate { FC2\_FRAMERATE\_1\_875, FC2\_FRAMERATE\_3\_75, FC2\_FRAMERATE\_7\_5, FC2\_FRAMERATE\_15, FC2\_FRAMERATE\_30, F-C2\_FRAMERATE\_60, FC2\_FRAMERATE\_120, FC2\_FRAMERATE\_240, F-C2\_FRAMERATE\_FORMAT7, FC2\_NUM\_FRAMERATES, FC2\_FRAMERATE FORCE 32BITS = FULL 32BIT VALUE }

#### Frame rates in frames per second.

enum fc2VideoMode { FC2\_VIDEOMODE\_160x120YUV444, FC2\_VIDEOMODE\_320x240YUV422, FC2\_VIDEOMODE\_640x480YUV411, FC2\_VIDEOMODE\_640x480YUV422, FC2\_VIDEOMODE\_640x480RGB, FC2\_VIDEOMODE\_640x480Y8, FC2\_VIDEOMODE\_640x480Y16, FC2\_VIDEOMODE\_800x600-YUV422, FC2\_VIDEOMODE\_800x600RGB, FC2\_VIDEOMODE\_800x600Y8, FC2\_VIDEOMODE\_800x600Y16, FC2\_VIDEOMODE\_1024x768YUV422, FC2\_VIDEOMODE\_1024x768RGB, FC2\_VIDEOMODE\_1024x768Y8, FC2\_VIDEOMODE\_1024x768Y16, FC2\_VIDEOMODE\_1280x960YUV422, FC2\_VIDEOMODE\_1280x960RGB, FC2\_VIDEOMODE\_1280x960Y16, FC2\_VIDEOMODE\_1280x960Y16, FC2\_VIDEOMODE\_1600x1200YUV422, FC2\_VIDEOMODE\_1600x1200YUV422, FC2\_VIDEOMODE\_1600x1200Y16, FC2\_VIDEOMODE\_1600x1200Y0V422, FC2\_VIDEOMODE\_1600x1200Y16, FC2\_VIDEOMODE\_1600x1200Y8, FC2\_VIDEOMODE\_1600x1200Y16, FC2\_VIDEOMODE\_FORMAT7, FC2\_NUM\_VIDEOMODES, FC2\_VIDEOMODE\_FORMAT7, FC2\_NUM\_VIDEOMODES, FC2\_VIDEOMODE\_FORMAT7

#### DCAM video modes.

enum fc2Mode { FC2\_MODE\_0 = 0, FC2\_MODE\_1, FC2\_MODE\_2, FC2\_MODE\_3, FC2\_MODE\_4, FC2\_MODE\_5, FC2\_MODE\_6, FC2\_MODE\_7, FC2\_MODE\_8, FC2\_MODE\_9, FC2\_MODE\_10, FC2\_MODE\_11, FC2\_MODE\_12, FC2\_MODE\_13, FC2\_MODE\_14, FC2\_MODE\_15, FC2\_MODE\_16, FC2\_MODE\_17, FC2\_MODE\_18, FC2\_MODE\_19, FC2\_MODE\_20, FC2\_MODE\_21, FC2\_MODE\_22, FC2\_MODE\_23, FC2\_MODE\_24, FC2\_MODE\_25, FC2\_MODE\_26, FC2\_MODE\_27, FC2\_MODE\_28, FC2\_MODE\_29, FC2\_MODE\_30, FC2\_MODE\_31, FC2\_NUM\_MODES, FC2\_MODE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

# Camera modes for DCAM formats as well as Format7.

enum fc2PixelFormat { FC2\_PIXEL\_FORMAT\_MONO8 = 0x80000000, F-C2\_PIXEL\_FORMAT\_411YUV8 = 0x40000000, FC2\_PIXEL\_FORMAT\_422-YUV8 = 0x20000000, FC2\_PIXEL\_FORMAT\_444YUV8 = 0x10000000, F-C2\_PIXEL\_FORMAT\_RGB8 = 0x08000000, FC2\_PIXEL\_FORMAT\_MONO16 = 0x04000000, FC2\_PIXEL\_FORMAT\_RGB16 = 0x020000000, FC2\_PIXEL\_FORMAT\_S MONO16 = 0x010000000, FC2\_PIXEL\_FORMAT\_S RGB16 =

6.22 Enumerations 109

0x00800000, FC2\_PIXEL\_FORMAT\_RAW8 = 0x00400000, FC2\_PIXEL\_FORMAT\_RAW16 = 0x00200000, FC2\_PIXEL\_FORMAT\_MONO12 = 0x00100000, FC2\_PIXEL\_FORMAT\_RAW12 = 0x00080000, FC2\_PIXEL\_FORMAT\_BGR = 0x80000008, FC2\_PIXEL\_FORMAT\_BGRU = 0x40000008, FC2\_PIXEL\_FORMAT\_RGBU = 0x40000008, FC2\_PIXEL\_FORMAT\_RGBU = 0x40000002, FC2\_PIXEL\_FORMAT\_RGBB, FC2\_PIXEL\_FORMAT\_RGBU = 0x40000002, FC2\_PIXEL\_FORMAT\_BGR16 = 0x02000001, FC2\_PIXEL\_FORMAT\_BGRU16 = 0x02000002, FC2\_PIXEL\_FORMAT\_422YUV8\_JPEG = 0x40000001, FC2\_NUM\_PIXEL\_FORMATS = 20, FC2\_UNSPECIFIED\_PIXEL\_FORMAT = 0 }

Pixel formats available for Format7 modes.

enum fc2BusSpeed { FC2\_BUSSPEED\_S100, FC2\_BUSSPEED\_S200, FC2\_BUSSPEED\_S400, FC2\_BUSSPEED\_S480, FC2\_BUSSPEED\_S800, FC2\_BUSSPEED\_S1600, FC2\_BUSSPEED\_S3200, FC2\_BUSSPEED\_S5000, × FC2\_BUSSPEED\_10BASE\_T, FC2\_BUSSPEED\_100BASE\_T, FC2\_BUSSPEED\_S2\_FASTEST, FC2\_BUSSPEED\_ANY, FC2\_BUSSPEED\_S2\_FASTEST, FC2\_BUSSPEED\_ANY, FC2\_BUSSPEED\_SPEED\_UNKNOWN = -1, FC2\_BUSSPEED\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Bus speeds.

- enum fc2PCleBusSpeed { FC2\_PCIE\_BUSSPEED\_2\_5, FC2\_PCIE\_BUSSPEED\_5\_0, FC2\_PCIE\_BUSSPEED\_UNKNOWN = -1, FC2\_PCIE\_BUSSPEED\_FORCE 32BITS = FULL 32BIT VALUE }
- enum fc2DriverType { FC2\_DRIVER\_1394\_CAM, FC2\_DRIVER\_1394\_PRO, FC2\_DRIVER\_1394\_JUJU, FC2\_DRIVER\_1394\_VIDEO1394, FC2\_DRIVER\_R\_1394\_RAW1394, FC2\_DRIVER\_USB\_NONE, FC2\_DRIVER\_USB\_CAM, FC2\_DRIVER\_USB3\_PRO, FC2\_DRIVER\_GIGE\_NONE, FC2\_DRIVER\_GIGE\_FILTER, FC2\_DRIVER\_GIGE\_PRO, FC2\_DRIVER\_GIGE\_LWF, FC2\_DRIVER\_UNKNOWN = -1, FC2\_DRIVER\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Types of low level drivers that FlyCapture uses.

enum fc2ColorProcessingAlgorithm { FC2\_DEFAULT, FC2\_NO\_COLOR\_PR-OCESSING, FC2\_NEAREST\_NEIGHBOR\_FAST, FC2\_EDGE\_SENSING, × FC2\_HQ\_LINEAR, FC2\_RIGOROUS, FC2\_IPP, FC2\_DIRECTIONAL, FC2\_WEIGHTED\_DIRECTIONAL, FC2\_COLOR\_PROCESSING\_ALGORITHM\_FO-RCE\_32BITS = FULL\_32BIT\_VALUE }

Color processing algorithms.

enum fc2BayerTileFormat { FC2\_BT\_NONE, FC2\_BT\_RGGB, FC2\_BT\_GRB-G, FC2\_BT\_GBRG, FC2\_BT\_BGGR, FC2\_BT\_FORCE\_32BITS = FULL\_32B-IT\_VALUE }

Bayer tile formats.

enum fc2ImageFileFormat { FC2\_FROM\_FILE\_EXT = -1, FC2\_PGM, FC2\_P-PM, FC2\_BMP, FC2\_JPEG, FC2\_JPEG2000, FC2\_TIFF, FC2\_PNG, FC2\_RAW, FC2\_IMAGE\_FILE\_FORMAT\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

File formats to be used for saving images to disk.

# 6.22.1 Enumeration Type Documentation

#### 6.22.1.1 enum fc2BandwidthAllocation

Bandwidth allocation options for 1394 devices.

#### **Enumerator:**

FC2\_BANDWIDTH\_ALLOCATION\_OFF Do not allocate bandwidth.

**FC2\_BANDWIDTH\_ALLOCATION\_ON** Allocate bandwidth. This is the default setting.

**FC2\_BANDWIDTH\_ALLOCATION\_UNSUPPORTED** Bandwidth allocation is not supported by either the camera or operating system.

**FC2\_BANDWIDTH\_ALLOCATION\_UNSPECIFIED** Not specified. This leaves the current setting unchanged.

FC2\_BANDWIDTH\_ALLOCATION\_FORCE\_32BITS

# 6.22.1.2 enum fc2BayerTileFormat

Bayer tile formats.

#### **Enumerator:**

FC2\_BT\_NONE No bayer tile format.

FC2\_BT\_RGGB Red-Green-Green-Blue.

FC2\_BT\_GRBG Green-Red-Blue-Green.

FC2\_BT\_GBRG Green-Blue-Red-Green.

FC2\_BT\_BGGR Blue-Green-Green-Red.

FC2\_BT\_FORCE\_32BITS

## 6.22.1.3 enum fc2BusCallbackType

The type of bus callback to register a callback function for.

# **Enumerator:**

FC2\_BUS\_RESET Register for all bus events.

FC2\_ARRIVAL Register for arrivals only.

FC2\_REMOVAL Register for removals only.

FC2\_CALLBACK\_TYPE\_FORCE\_32BITS

6.22 Enumerations 111

#### 6.22.1.4 enum fc2BusSpeed

#### Bus speeds.

## **Enumerator:**

```
FC2 BUSSPEED S100 100Mbits/sec.
```

FC2\_BUSSPEED\_S200 200Mbits/sec.

FC2\_BUSSPEED\_S400 400Mbits/sec.

FC2\_BUSSPEED\_S480 480Mbits/sec. Only for USB2 cameras.

FC2\_BUSSPEED\_S800 800Mbits/sec.

FC2\_BUSSPEED\_S1600 1600Mbits/sec.

FC2\_BUSSPEED\_S3200 3200Mbits/sec.

FC2\_BUSSPEED\_S5000 5000Mbits/sec. Only for USB3 cameras.

FC2\_BUSSPEED\_10BASE\_T 10Base-T. Only for GigE cameras.

FC2\_BUSSPEED\_100BASE\_T 100Base-T. Only for GigE cameras.

**FC2\_BUSSPEED\_1000BASE\_T** 1000Base-T (Gigabit Ethernet). Only for GigE cameras.

FC2\_BUSSPEED\_10000BASE\_T 10000Base-T. Only for GigE cameras.

FC2\_BUSSPEED\_S\_FASTEST The fastest speed available.

FC2\_BUSSPEED\_ANY Any speed that is available.

FC2\_BUSSPEED\_SPEED\_UNKNOWN Unknown bus speed.

FC2 BUSSPEED FORCE 32BITS

## 6.22.1.5 enum fc2ColorProcessingAlgorithm

Color processing algorithms.

Please refer to our knowledge base at article at http://www.ptgrey.-com/support/kb/index.asp?a=4&q=33 for complete details for each algorithm.

## **Enumerator:**

FC2\_DEFAULT Default method.

FC2\_NO\_COLOR\_PROCESSING No color processing.

**FC2\_NEAREST\_NEIGHBOR\_FAST** Fastest but lowest quality. Equivalent to F-LYCAPTURE NEAREST NEIGHBOR FAST in FlyCapture.

**FC2\_EDGE\_SENSING** Weights surrounding pixels based on localized edge orientation.

FC2\_HQ\_LINEAR Well-balanced speed and quality.

FC2\_RIGOROUS Slowest but produces good results.

FC2\_IPP Multithreaded with similar results to edge sensing.

FC2\_DIRECTIONAL Best quality but much faster than rigorous.

**FC2\_WEIGHTED\_DIRECTIONAL** Weighted pixel average from different directions.

FC2\_COLOR\_PROCESSING\_ALGORITHM\_FORCE\_32BITS

## 6.22.1.6 enum fc2DriverType

Types of low level drivers that FlyCapture uses.

#### **Enumerator:**

FC2\_DRIVER\_1394\_CAM PGRCam.sys.

FC2\_DRIVER\_1394\_PRO PGR1394.sys.

FC2\_DRIVER\_1394\_JUJU firewire core.

FC2\_DRIVER\_1394\_VIDEO1394 video1394.

FC2\_DRIVER\_1394\_RAW1394 raw1394.

FC2\_DRIVER\_USB\_NONE No usb driver used just BSD stack. (Linux only)

FC2\_DRIVER\_USB\_CAM PGRUsbCam.sys.

FC2\_DRIVER\_USB3\_PRO PGRXHCI.sys.

FC2\_DRIVER\_GIGE\_NONE no GigE drivers used, MS/BSD stack.

FC2\_DRIVER\_GIGE\_FILTER PGRGigE.sys.

FC2\_DRIVER\_GIGE\_PRO PGRGigEPro.sys.

FC2\_DRIVER\_GIGE\_LWF PgrLwf.sys.

FC2\_DRIVER\_UNKNOWN Unknown driver type.

FC2\_DRIVER\_FORCE\_32BITS

# 6.22.1.7 enum fc2Error

The error types returned by functions.

## **Enumerator:**

FC2\_ERROR\_UNDEFINED Undefined.

FC2\_ERROR\_OK Function returned with no errors.

FC2\_ERROR\_FAILED General failure.

FC2\_ERROR\_NOT\_IMPLEMENTED Function has not been implemented.

**FC2\_ERROR\_FAILED\_BUS\_MASTER\_CONNECTION** Could not connect to - Bus Master.

FC2\_ERROR\_NOT\_CONNECTED Camera has not been connected.

FC2\_ERROR\_INIT\_FAILED Initialization failed.

FC2\_ERROR\_NOT\_INTITIALIZED Camera has not been initialized.

6.22 Enumerations 113

- FC2 ERROR INVALID PARAMETER Invalid parameter passed to function.
- FC2\_ERROR\_INVALID\_SETTINGS Setting set to camera is invalid.
- FC2\_ERROR\_INVALID\_BUS\_MANAGER Invalid Bus Manager object.
- FC2\_ERROR\_MEMORY\_ALLOCATION\_FAILED Could not allocate memory.
- FC2\_ERROR\_LOW\_LEVEL\_FAILURE Low level error.
- FC2\_ERROR\_NOT\_FOUND Device not found.
- FC2 ERROR FAILED GUID GUID failure.
- FC2\_ERROR\_INVALID\_PACKET\_SIZE Packet size set to camera is invalid.
- FC2 ERROR INVALID MODE Invalid mode has been passed to function.
- FC2\_ERROR\_NOT\_IN\_FORMAT7 Error due to not being in Format7.
- FC2\_ERROR\_NOT\_SUPPORTED This feature is unsupported.
- FC2\_ERROR\_TIMEOUT Timeout error.
- FC2\_ERROR\_BUS\_MASTER\_FAILED Bus Master Failure.
- FC2\_ERROR\_INVALID\_GENERATION Generation Count Mismatch.
- FC2\_ERROR\_LUT\_FAILED Look Up Table failure.
- FC2 ERROR IIDC FAILED IIDC failure.
- FC2\_ERROR\_STROBE\_FAILED Strobe failure.
- FC2\_ERROR\_TRIGGER\_FAILED Trigger failure.
- FC2\_ERROR\_PROPERTY\_FAILED Property failure.
- FC2\_ERROR\_PROPERTY\_NOT\_PRESENT Property is not present.
- FC2\_ERROR\_REGISTER\_FAILED Register access failed.
- FC2\_ERROR\_READ\_REGISTER\_FAILED Register read failed.
- FC2\_ERROR\_WRITE\_REGISTER\_FAILED Register write failed.
- FC2\_ERROR\_ISOCH\_FAILED Isochronous failure.
- **FC2\_ERROR\_ISOCH\_ALREADY\_STARTED** Isochronous transfer has already been started.
- **FC2\_ERROR\_ISOCH\_NOT\_STARTED** Isochronous transfer has not been started.
- FC2\_ERROR\_ISOCH\_START\_FAILED Isochronous start failed.
- **FC2\_ERROR\_ISOCH\_RETRIEVE\_BUFFER\_FAILED** Isochronous retrieve buffer failed.
- FC2\_ERROR\_ISOCH\_STOP\_FAILED Isochronous stop failed.
- **FC2\_ERROR\_ISOCH\_SYNC\_FAILED** Isochronous image synchronization failed.
- **FC2\_ERROR\_ISOCH\_BANDWIDTH\_EXCEEDED** Isochronous bandwidth exceeded.
- FC2\_ERROR\_IMAGE\_CONVERSION\_FAILED Image conversion failed.
- FC2 ERROR IMAGE LIBRARY FAILURE Image library failure.
- FC2\_ERROR\_BUFFER\_TOO\_SMALL Buffer is too small.

FC2\_ERROR\_IMAGE\_CONSISTENCY\_ERROR There is an image consistency error.

**FC2\_ERROR\_INCOMPATIBLE\_DRIVER** The installed driver is not compatible with the library.

FC2\_ERROR\_FORCE\_32BITS

#### 6.22.1.8 enum fc2FrameRate

Frame rates in frames per second.

#### **Enumerator:**

**FC2\_FRAMERATE\_1\_875** 1.875 fps.

FC2 FRAMERATE 3 75 3.75 fps.

FC2\_FRAMERATE\_7\_5 7.5 fps.

FC2\_FRAMERATE\_15 15 fps.

FC2\_FRAMERATE\_30 30 fps.

FC2\_FRAMERATE\_60 60 fps.

FC2\_FRAMERATE\_120 120 fps.

FC2\_FRAMERATE\_240 240 fps.

FC2\_FRAMERATE\_FORMAT7 Custom frame rate for Format7 functionality.

**FC2\_NUM\_FRAMERATES** Number of possible camera frame rates.

FC2\_FRAMERATE\_FORCE\_32BITS

## 6.22.1.9 enum fc2GrabMode

The grab strategy employed during image transfer.

This type controls how images that stream off the camera accumulate in a user buffer for handling.

#### **Enumerator:**

FC2\_DROP\_FRAMES Grabs the newest image in the user buffer each time the RetrieveBuffer() function is called. Older images are dropped instead of accumulating in the user buffer. Grabbing blocks if the camera has not finished transmitting the next available image. If the camera is transmitting images faster than the application can grab them, images may be dropped and only the most recent image is stored for grabbing. Note that this mode is the equivalent of flycaptureLockLatest in earlier versions of the FlyCapture SDK.

**FC2\_BUFFER\_FRAMES** Images accumulate in the user buffer, and the oldest image is grabbed for handling before being discarded. This member can be used to guarantee that each image is seen. However, image processing time must not exceed transmission time from the camera to the buffer. Grabbing

6.22 Enumerations 115

blocks if the camera has not finished transmitting the next available image. The buffer size is controlled by the numBuffers parameter in the FC2Config struct. Note that this mode is the equivalent of flycaptureLockNext in earlier versions of the FlyCapture SDK.

FC2\_UNSPECIFIED\_GRAB\_MODE Unspecified grab mode.
FC2\_GRAB\_MODE\_FORCE\_32BITS

#### 6.22.1.10 enum fc2GrabTimeout

Timeout options for grabbing images.

## **Enumerator:**

FC2\_TIMEOUT\_NONE Non-blocking wait.

FC2\_TIMEOUT\_INFINITE Wait indefinitely.

FC2\_TIMEOUT\_UNSPECIFIED Unspecified timeout setting.

FC2\_GRAB\_TIMEOUT\_FORCE\_32BITS

## 6.22.1.11 enum fc2ImageFileFormat

File formats to be used for saving images to disk.

## **Enumerator:**

FC2\_FROM\_FILE\_EXT Determine file format from file extension.

FC2\_PGM Portable gray map.

FC2\_PPM Portable pixmap.

FC2\_BMP Bitmap.

FC2\_JPEG JPEG.

FC2\_JPEG2000 JPEG 2000.

FC2\_TIFF Tagged image file format.

FC2\_PNG Portable network graphics.

FC2\_RAW Raw data.

FC2\_IMAGE\_FILE\_FORMAT\_FORCE\_32BITS

# 6.22.1.12 enum fc2InterfaceType

Interfaces that a camera may use to communicate with a host.

## Enumerator:

FC2\_INTERFACE\_IEEE1394 | IEEE-1394 (Includes 1394a and 1394b).

```
FC2_INTERFACE_USB_2 USB 2.0.
FC2_INTERFACE_USB_3 USB 3.0.
FC2_INTERFACE_GIGE GigE.
FC2_INTERFACE_UNKNOWN Unknown interface.
FC2_INTERFACE_TYPE_FORCE_32BITS
```

## 6.22.1.13 enum fc2Mode

Camera modes for DCAM formats as well as Format7.

# Enumerator:

```
FC2_MODE_0
FC2_MODE_1
FC2_MODE_2
FC2_MODE_3
FC2_MODE_4
FC2_MODE_5
FC2_MODE_6
FC2_MODE_7
FC2_MODE_8
FC2_MODE_9
FC2_MODE_10
FC2_MODE_11
FC2_MODE_12
FC2_MODE_13
FC2_MODE_14
FC2_MODE_15
FC2_MODE_16
FC2_MODE_17
FC2_MODE_18
FC2_MODE_19
FC2_MODE_20
FC2_MODE_21
FC2_MODE_22
FC2_MODE_23
FC2_MODE_24
FC2_MODE_25
```

FC2\_MODE\_26

6.22 Enumerations 117

```
FC2 MODE 27
```

FC2\_MODE\_28

FC2 MODE 29

FC2\_MODE\_30

FC2 MODE 31

FC2\_NUM\_MODES Number of modes.

FC2\_MODE\_FORCE\_32BITS

#### 6.22.1.14 enum fc2PCleBusSpeed

#### **Enumerator:**

FC2\_PCIE\_BUSSPEED\_2\_5

FC2\_PCIE\_BUSSPEED\_5\_0 2.5 Gb/s

FC2\_PCIE\_BUSSPEED\_UNKNOWN 5.0 Gb/s

FC2\_PCIE\_BUSSPEED\_FORCE\_32BITS Speed is unknown.

#### 6.22.1.15 enum fc2PixelFormat

Pixel formats available for Format7 modes.

## **Enumerator:**

FC2\_PIXEL\_FORMAT\_MONO8 8 bits of mono information.

FC2 PIXEL FORMAT 411YUV8 YUV 4:1:1.

FC2\_PIXEL\_FORMAT\_422YUV8 YUV 4:2:2.

FC2 PIXEL FORMAT 444YUV8 YUV 4:4:4.

 $FC2\_PIXEL\_FORMAT\_RGB8$  R = G = B = 8 bits.

FC2\_PIXEL\_FORMAT\_MONO16 16 bits of mono information.

 $FC2\_PIXEL\_FORMAT\_RGB16$  R = G = B = 16 bits.

FC2\_PIXEL\_FORMAT\_S\_MONO16 16 bits of signed mono information.

 $FC2\_PIXEL\_FORMAT\_S\_RGB16$  R = G = B = 16 bits signed.

FC2\_PIXEL\_FORMAT\_RAW8 8 bit raw data output of sensor.

FC2\_PIXEL\_FORMAT\_RAW16 16 bit raw data output of sensor.

FC2\_PIXEL\_FORMAT\_MONO12 12 bits of mono information.

FC2\_PIXEL\_FORMAT\_RAW12 12 bit raw data output of sensor.

FC2\_PIXEL\_FORMAT\_BGR 24 bit BGR.

FC2\_PIXEL\_FORMAT\_BGRU 32 bit BGRU.

FC2 PIXEL FORMAT RGB 24 bit RGB.

FC2\_PIXEL\_FORMAT\_RGBU 32 bit RGBU.

FC2\_PIXEL\_FORMAT\_BGR16 R = G = B = 16 bits.

FC2\_PIXEL\_FORMAT\_BGRU16 64 bit BGRU.

FC2\_PIXEL\_FORMAT\_422YUV8\_JPEG JPEG compressed stream.

FC2\_NUM\_PIXEL\_FORMATS Number of pixel formats.

FC2\_UNSPECIFIED\_PIXEL\_FORMAT Unspecified pixel format.

# 6.22.1.16 enum fc2PropertyType

# Camera properties.

Not all properties may be supported, depending on the camera model.

## **Enumerator:**

FC2\_BRIGHTNESS

FC2\_AUTO\_EXPOSURE

FC2\_SHARPNESS

FC2\_WHITE\_BALANCE

FC2\_HUE

FC2\_SATURATION

FC2\_GAMMA

FC2 IRIS

FC2\_FOCUS

FC2\_ZOOM

FC2\_PAN

FC2\_TILT

FC2\_SHUTTER

FC2\_GAIN

FC2\_TRIGGER\_MODE

FC2\_TRIGGER\_DELAY

FC2\_FRAME\_RATE

FC2\_TEMPERATURE

FC2\_UNSPECIFIED\_PROPERTY\_TYPE

FC2\_PROPERTY\_TYPE\_FORCE\_32BITS

## 6.22.1.17 enum fc2VideoMode

DCAM video modes.

# **Enumerator:**

FC2\_VIDEOMODE\_160x120YUV444 160x120 YUV444.

6.22 Enumerations 119

- FC2 VIDEOMODE 320x240YUV422 320x240 YUV422.
- FC2\_VIDEOMODE\_640x480YUV411 640x480 YUV411.
- FC2\_VIDEOMODE\_640x480YUV422 640x480 YUV422.
- FC2\_VIDEOMODE\_640x480RGB 640x480 24-bit RGB.
- FC2\_VIDEOMODE\_640x480Y8 640x480 8-bit.
- FC2\_VIDEOMODE\_640x480Y16 640x480 16-bit.
- FC2 VIDEOMODE 800x600YUV422 800x600 YUV422.
- FC2\_VIDEOMODE\_800x600RGB 800x600 RGB.
- FC2 VIDEOMODE 800x600Y8 800x600 8-bit.
- FC2 VIDEOMODE 800x600Y16 800x600 16-bit.
- FC2\_VIDEOMODE\_1024x768YUV422 1024x768 YUV422.
- FC2\_VIDEOMODE\_1024x768RGB 1024x768 RGB.
- FC2\_VIDEOMODE\_1024x768Y8 1024x768 8-bit.
- FC2\_VIDEOMODE\_1024x768Y16 1024x768 16-bit.
- FC2\_VIDEOMODE\_1280x960YUV422 1280x960YUV422.
- FC2\_VIDEOMODE\_1280x960RGB 1280x960 RGB.
- FC2\_VIDEOMODE\_1280x960Y8 1280x960 8-bit.
- FC2\_VIDEOMODE\_1280x960Y16 1280x960 16-bit.
- FC2\_VIDEOMODE\_1600x1200YUV422 1600x1200 YUV422.
- FC2\_VIDEOMODE\_1600x1200RGB 1600x1200 RGB.
- FC2\_VIDEOMODE\_1600x1200Y8 1600x1200 8-bit.
- FC2\_VIDEOMODE\_1600x1200Y16 1600x1200 16-bit.
- FC2\_VIDEOMODE\_FORMAT7 Custom video mode for Format7 functionality.
- FC2\_NUM\_VIDEOMODES Number of possible video modes.
- FC2\_VIDEOMODE\_FORCE\_32BITS

## 6.23 GigE specific enumerations

These enumerations are specific to GigE camera operation only.

#### **Enumerations**

 enum fc2GigEPropertyType { FC2\_HEARTBEAT, FC2\_HEARTBEAT\_TIMEO-UT, PACKET\_SIZE, PACKET\_DELAY }

Possible properties that can be queried from the camera.

## 6.23.1 Detailed Description

These enumerations are specific to GigE camera operation only.

## 6.23.2 Enumeration Type Documentation

#### 6.23.2.1 enum fc2GigEPropertyType

Possible properties that can be queried from the camera.


#### **Enumerator:**

FC2\_HEARTBEAT
FC2\_HEARTBEAT\_TIMEOUT
PACKET\_SIZE
PACKET\_DELAY

6.24 Structures 121

## 6.24 Structures

Collaboration diagram for Structures:



#### **Data Structures**

- struct fc2lmage
- struct fc2SystemInfo

Description of the system.

struct fc2Version

The current version of the library.

• struct fc2IPAddress

IPv4 address.

• struct fc2Format7ImageSettings

Format 7 image settings.

struct fc2Config

Configuration for a camera.

• struct fc2TriggerDelayInfo

Information about a specific camera property.

struct fc2TriggerDelay

A specific camera property.

• struct fc2TriggerModeInfo

Information about a camera trigger property.

• struct fc2TriggerMode

A camera trigger.

• struct fc2StrobeInfo

A camera strobe property.

struct fc2StrobeControl

A camera strobe.

struct fc2TimeStamp

Timestamp information.

• struct fc2ConfigROM

Camera configuration ROM.

struct fc2CameraInfo

Camera information.

struct fc2EmbeddedImageInfoProperty

Properties of a single embedded image info property.

• struct fc2EmbeddedImageInfo

Properties of the possible embedded image information.

• struct fc2lmageMetadata

Metadata related to an image.

struct fc2LUTData

Information about the camera's look up table.

struct fc2CameraStats

Camera diagnostic information.

• struct fc2PNGOption

Options for saving PNG images.

• struct fc2MJPGOption

Options for saving MJPG files.

#### Modules

· GigE specific structures

These structures are specific to GigE camera operation only.

• IIDC specific structures

These structures are specific to IIDC camera operation only.

· Image saving structures.

These structures define various parameters used for saving images.

Video saving structures.

These structures define various parameters used for saving videos.

## 6.25 GigE specific structures

These structures are specific to GigE camera operation only.

Collaboration diagram for GigE specific structures:



#### **Data Structures**

struct fc2IPAddress

IPv4 address.

• struct fc2MACAddress

MAC address.

struct fc2GigEProperty

A GigE property.

• struct fc2GigEStreamChannel

Information about a single GigE stream channel.

• struct fc2GigEConfig

Configuration for a GigE camera.

• struct fc2GigEImageSettingsInfo

Format 7 information for a single mode.

• struct fc2GigEImageSettings

Image settings for a GigE camera.

## 6.25.1 Detailed Description

These structures are specific to GigE camera operation only.

## 6.26 IIDC specific structures

These structures are specific to IIDC camera operation only.

Collaboration diagram for IIDC specific structures:



## **Data Structures**

- struct fc2Format7ImageSettings
  - Format 7 image settings.
- struct fc2Format7Info
  - Format 7 information for a single mode.
- struct fc2Format7PacketInfo

Format 7 packet information.

## 6.26.1 Detailed Description

These structures are specific to IIDC camera operation only.

## 6.27 Image saving structures.

These structures define various parameters used for saving images.

Collaboration diagram for Image saving structures.:



#### **Data Structures**

• struct fc2PNGOption

Options for saving PNG images.

• struct fc2PPMOption

Options for saving PPM images.

• struct fc2PGMOption

Options for saving PGM images.

struct fc2TIFFOption

Options for saving TIFF images.

• struct fc2JPEGOption

Options for saving JPEG image.

• struct fc2JPG2Option

Options for saving JPEG2000 image.

struct fc2BMPOption

Options for saving Bitmap image.

struct fc2EventOptions

Options for enabling device event registration.

• struct fc2EventCallbackData

## **Typedefs**

- typedef void \* fc2CallbackHandle
- typedef void(\* fc2BusEventCallback )(void \*pParameter, unsigned int serial-Number)
- typedef void(\* fc2ImageEventCallback)(fc2Image \*image, void \*pCallbackData)
- typedef void(\* fc2AsyncCommandCallback )(fc2Error retError, void \*pUserData)
- typedef void(\* fc2CameraEventCallback )(void \*pCallbackData)

#### **Enumerations**

enum fc2TIFFCompressionMethod { FC2\_TIFF\_NONE = 1, FC2\_TIFF\_PACK-BITS, FC2\_TIFF\_DEFLATE, FC2\_TIFF\_ADOBE\_DEFLATE, FC2\_TIFF\_CCI-TTFAX3, FC2\_TIFF\_CCITTFAX4, FC2\_TIFF\_LZW, FC2\_TIFF\_JPEG }

#### 6.27.1 Detailed Description

These structures define various parameters used for saving images.

- 6.27.2 Typedef Documentation
- 6.27.2.1 typedef void(\* fc2AsyncCommandCallback)(fc2Error retError, void \*pUserData)
- 6.27.2.2 typedef void(\* fc2BusEventCallback)(void \*pParameter, unsigned int serialNumber)
- 6.27.2.3 typedef void\* fc2CallbackHandle
- 6.27.2.4 typedef void(\* fc2CameraEventCallback)(void \*pCallbackData)
- 6.27.2.5 typedef void(\* fc2ImageEventCallback)(fc2Image \*image, void \*pCallbackData)
- 6.27.3 Enumeration Type Documentation
- 6.27.3.1 enum fc2TIFFCompressionMethod

#### **Enumerator:**

- FC2\_TIFF\_NONE Save without any compression.
- FC2\_TIFF\_PACKBITS Save using PACKBITS compression.
- FC2\_TIFF\_DEFLATE Save using DEFLATE compression (ZLIB compression).
- FC2\_TIFF\_ADOBE\_DEFLATE Save using ADOBE DEFLATE compression.
- **FC2\_TIFF\_CCITTFAX3** Save using CCITT Group 3 fax encoding. This is only valid for 1-bit images only. Default to LZW for other bit depths.
- **FC2\_TIFF\_CCITTFAX4** Save using CCITT Group 4 fax encoding. This is only valid for 1-bit images only. Default to LZW for other bit depths.
- FC2\_TIFF\_LZW Save using LZW compression.
- **FC2\_TIFF\_JPEG** Save using JPEG compression. This is only valid for 8-bit greyscale and 24-bit only. Default to LZW for other bit depths.

## 6.28 Video Recording Operation

The video recording operation provides the functionality for the user to record images to an video file.

#### **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2VideoCreate (fc2VideoContext \*pVideo-Context)

Create a Video context.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoAVIOpen (fc2VideoContext Video-Context, const char \*pFileName, fc2AVIOption \*pOption)

Open an AVI file in preparation for writing Images to disk.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoMJPGOpen (fc2VideoContext Video-Context, const char \*pFileName, fc2MJPGOption \*pOption)

Open an MJPEG file in preparation for writing Images to disk.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoH264Open (fc2VideoContext Video-Context, const char \*pFileName, fc2H264Option \*pOption)

Open an H.264 video file in preparation for writing Images to disk.

FLYCAPTURE2\_C\_API fc2Error fc2VideoAppend (fc2VideoContext Video-Context, fc2Image \*pImage)

Append an image to the video file.

FLYCAPTURE2\_C\_API fc2Error fc2VideoSetMaximumSize (fc2VideoContext - VideoContext, unsigned int size)

Set the maximum file size (in megabytes) of a AVI/MP4 file.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoClose (fc2VideoContext Video-Context)

Close the video file.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoDestroy (fc2VideoContext Video-Context)

Destroy a video context.

#### 6.28.1 Detailed Description

The video recording operation provides the functionality for the user to record images to an video file.

#### 6.28.2 Function Documentation

6.28.2.1 FLYCAPTURE2\_C\_API fc2Error fc2VideoAppend ( fc2VideoContext VideoContext, fc2Image \* plmage )

Append an image to the video file.

#### **Parameters**

Video-	The video context to use.
Context	
plmage	The image to append.

#### Returns

A fc2Error indicating the success or failure of the function.

6.28.2.2 FLYCAPTURE2\_C\_API fc2Error fc2VideoAVIOpen ( fc2VideoContext *VideoContext*, const char \* *pFileName*, fc2AVIOption \* *pOption* )

Open an AVI file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

#### **Parameters**

Video-	The video context to use.
Context	
pFileName	The filename of the AVI file.
pOption	Options to apply to the AVI file.

## See also

SetMaximumFileSize() fc2Close() fc2AVIOption

## Returns

A fc2Error indicating the success or failure of the function.

6.28.2.3 FLYCAPTURE2\_C\_API fc2Error fc2VideoClose ( fc2VideoContext VideoContext )

Close the video file.

#### **Parameters**

Video-	The video context to use.
Context	

#### Returns

A fc2Error indicating the success or failure of the function.

## 6.28.2.4 FLYCAPTURE2\_C\_API fc2Error fc2VideoCreate ( fc2VideoContext \* pVideoContext )

Create a Video context.

#### **Parameters**

pVideo-	A video context.
Context	

#### **Returns**

A fc2Error indicating the success or failure of the function.

## 6.28.2.5 FLYCAPTURE2\_C\_API fc2Error fc2VideoDestroy ( fc2VideoContext VideoContext )

Destroy a video context.

#### **Parameters**

Video-	A video context.
Context	

#### **Returns**

A fc2Error indicating the success or failure of the function.

## 

Open an H.264 video file in preparation for writing Images to disk.

If the file extension is not specified, MP4 will be used as the default container. Consult ffmpeg documentation for a list of supported containers.

#### **Parameters**

pFileName	The filename of the video file.
pOption	H.264 options to apply to the video file.

#### See also

fc2Close() fc2H264Option

#### Returns

A fc2Error indicating the success or failure of the function.

# 6.28.2.7 FLYCAPTURE2\_C\_API fc2Error fc2VideoMJPGOpen ( fc2VideoContext VideoContext, const char \* pFileName, fc2MJPGOption \* pOption )

Open an MJPEG file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

#### **Parameters**

Video-	The AVI context to use.
Context	
pFileName	The filename of the AVI file.
pOption	Options to apply to the AVI file.

#### See also

fc2Close() fc2MJPGOption

#### Returns

A fc2Error indicating the success or failure of the function.

## 

Set the maximum file size (in megabytes) of a AVI/MP4 file.

A new AVI/MP4 file is created automatically when file size limit is reached. Setting a maximum size of 0 indicates no limit on file size.

#### **Parameters**

Video-	The video context to use.
Context	
size	The maximum video file size in MB.

#### Returns

A fc2Error indicating the success or failure of the function.

## 6.29 Video saving structures.

These structures define various parameters used for saving videos.

Collaboration diagram for Video saving structures.:



## **Data Structures**

- struct fc2MJPGOption
  - Options for saving MJPG files.
- struct fc2H264Option
  - Options for saving H264 files.
- struct fc2AVIOption

Options for saving AVI files.

## 6.29.1 Detailed Description

These structures define various parameters used for saving videos.

## **Chapter 7**

## **Data Structure Documentation**

## 7.1 fc2AVIOption Struct Reference

Options for saving AVI files.

#### **Data Fields**

float frameRate

Frame rate of the stream.

• unsigned int reserved [256]

Reserved for future use.

## 7.1.1 Detailed Description

Options for saving AVI files.

#### 7.1.2 Field Documentation

## 7.1.2.1 float frameRate

Frame rate of the stream.

## 7.1.2.2 unsigned int reserved[256]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2VideoDefs\_C.h

## 7.2 fc2BMPOption Struct Reference

Options for saving Bitmap image.

#### **Data Fields**

- BOOL indexedColor\_8bit
- unsigned int reserved [16]

Reserved for future use.

## 7.2.1 Detailed Description

Options for saving Bitmap image.

#### 7.2.2 Field Documentation

- 7.2.2.1 BOOL indexedColor\_8bit
- 7.2.2.2 unsigned int reserved[16]

Reserved for future use.


The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.3 fc2CameraInfo Struct Reference

Camera information.

Collaboration diagram for fc2CameraInfo:



#### **Data Fields**

• unsigned int serialNumber

Device serial number.

fc2InterfaceType interfaceType

Interface type.

• fc2DriverType driverType

Driver type.

• BOOL isColorCamera

Flag indicating if this is a color camera.

• char modelName [MAX STRING LENGTH]

Device model name.

• char vendorName [MAX\_STRING\_LENGTH]

Device vendor name.

• char sensorInfo [MAX\_STRING\_LENGTH]

String detailing the sensor information.

char sensorResolution [MAX\_STRING\_LENGTH]

String providing the sensor resolution.

char driverName [MAX\_STRING\_LENGTH]

Driver name of driver being used.

char firmwareVersion [MAX\_STRING\_LENGTH]

Firmware version of camera.

• char firmwareBuildTime [MAX\_STRING\_LENGTH]

Firmware build time.

fc2BusSpeed maximumBusSpeed

Maximum bus speed.

fc2BayerTileFormat bayerTileFormat

Bayer tile format.

• fc2PCleBusSpeed pcieBusSpeed

Bus number, set to 0 for GigE and USB cameras.

unsigned short nodeNumber

ieee1394 Node number, set to 0 for GigE and USB cameras

• unsigned short busNumber

PCIe Bus Speed, set to PCIE\_BUSSPEED\_UNKNOWN for unsupported drivers.

• unsigned int reserved [16]

Reserved for future use.

#### **IIDC** specific information

· unsigned int iidcVer

DCAM version.

fc2ConfigROM configROM

Configuration ROM data.

#### GigE specific information

• unsigned int gigEMajorVersion

GigE Vision version.

unsigned int gigEMinorVersion

GigE Vision minor version.

char userDefinedName [MAX STRING LENGTH]

User defined name.

char xmlURL1 [MAX\_STRING\_LENGTH]

XML URL 1.

char xmlURL2 [MAX\_STRING\_LENGTH]

XML URL 2.

• fc2MACAddress macAddress

MAC address.

• fc2IPAddress ipAddress

IP address.

· fc2IPAddress subnetMask

Subnet mask.

· fc2IPAddress defaultGateway

Default gateway.

unsigned int ccpStatus

Status/Content of CCP register.

· unsigned int applicationIPAddress

Local Application IP Address.

• unsigned int applicationPort

Local Application port.

### 7.3.1 Detailed Description

Camera information.

#### 7.3.2 Field Documentation

7.3.2.1 unsigned int applicationIPAddress

Local Application IP Address.

7.3.2.2 unsigned int applicationPort

Local Application port.

7.3.2.3 fc2BayerTileFormat bayerTileFormat

Bayer tile format.

7.3.2.4 unsigned short busNumber

PCIe Bus Speed, set to PCIE\_BUSSPEED\_UNKNOWN for unsupported drivers.

7.3.2.5 unsigned int ccpStatus

Status/Content of CCP register.

7.3.2.6 fc2ConfigROM configROM

Configuration ROM data.

7.3.2.7 fc2IPAddress defaultGateway

Default gateway.

7.3.2.8 char driverName[MAX\_STRING\_LENGTH]

Driver name of driver being used.

7.3.2.9 fc2DriverType driverType

Driver type.

7.3.2.10 char firmwareBuildTime[MAX\_STRING\_LENGTH]

Firmware build time.

#### 7.3.2.11 char firmwareVersion[MAX\_STRING\_LENGTH]

Firmware version of camera.

7.3.2.12 unsigned int gigEMajorVersion

GigE Vision version.

7.3.2.13 unsigned int gigEMinorVersion

GigE Vision minor version.

7.3.2.14 unsigned int iidcVer

DCAM version.

7.3.2.15 fc2InterfaceType interfaceType

Interface type.

7.3.2.16 fc2IPAddress ipAddress

IP address.

7.3.2.17 BOOL isColorCamera

Flag indicating if this is a color camera.

7.3.2.18 fc2MACAddress macAddress

MAC address.

7.3.2.19 fc2BusSpeed maximumBusSpeed

Maximum bus speed.

7.3.2.20 char modelName[MAX\_STRING\_LENGTH]

Device model name.

7.3.2.21 unsigned short nodeNumber

ieee1394 Node number, set to 0 for GigE and USB cameras

7.3.2.22 fc2PCleBusSpeed pcieBusSpeed

Bus number, set to 0 for GigE and USB cameras.

7.3.2.23 unsigned int reserved[16]

Reserved for future use.

7.3.2.24 char sensorInfo[MAX\_STRING\_LENGTH]

String detailing the sensor information.

7.3.2.25 char sensorResolution[MAX\_STRING\_LENGTH]

String providing the sensor resolution.

7.3.2.26 unsigned int serialNumber

Device serial number.

7.3.2.27 fc2IPAddress subnetMask

Subnet mask.

7.3.2.28 char userDefinedName[MAX\_STRING\_LENGTH]

User defined name.

7.3.2.29 char vendorName[MAX\_STRING\_LENGTH]

Device vendor name.

7.3.2.30 char xmIURL1[MAX\_STRING\_LENGTH]

XML URL 1.

#### 7.3.2.31 char xmIURL2[MAX\_STRING\_LENGTH]

#### XML URL 2.


The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

#### 7.4 fc2CameraStats Struct Reference

Camera diagnostic information.

Collaboration diagram for fc2CameraStats:



#### **Data Fields**

- unsigned int imageDropped
- unsigned int imageCorrupt
- · unsigned int imageXmitFailed
- unsigned int imageDriverDropped
- unsigned int regReadFailed
- unsigned int regWriteFailed
- unsigned int portErrors
- BOOL cameraPowerUp
- float cameraVoltages [8]
- unsigned int numVoltages

The number of voltage registers available.

- float cameraCurrents [8]
- · unsigned int numCurrents

The number of current registers available.

- · unsigned int temperature
- unsigned int timeSinceInitialization
- unsigned int timeSinceBusReset
- fc2TimeStamp timeStamp
- · unsigned int numResendPacketsRequested
- · unsigned int numResendPacketsReceived
- unsigned int reserved [16]

Reserved for future use.

#### 7.4.1 Detailed Description

Camera diagnostic information.

- 7.4.2 Field Documentation
- 7.4.2.1 float cameraCurrents[8]
- 7.4.2.2 BOOL cameraPowerUp
- 7.4.2.3 float cameraVoltages[8]
- 7.4.2.4 unsigned int imageCorrupt
- 7.4.2.5 unsigned int imageDriverDropped
- 7.4.2.6 unsigned int imageDropped
- 7.4.2.7 unsigned int imageXmitFailed
- 7.4.2.8 unsigned int numCurrents

The number of current registers available.

0: the values in cameraCurrents[] are invalid.

- 7.4.2.9 unsigned int numResendPacketsReceived
- 7.4.2.10 unsigned int numResendPacketsRequested
- 7.4.2.11 unsigned int numVoltages

The number of voltage registers available.

0: the values in cameraVoltages[] are invalid.

- 7.4.2.12 unsigned int portErrors
- 7.4.2.13 unsigned int regReadFailed
- 7.4.2.14 unsigned int regWriteFailed
- 7.4.2.15 unsigned int reserved[16]

Reserved for future use.

- 7.4.2.16 unsigned int temperature
- 7.4.2.17 unsigned int timeSinceBusReset
- 7.4.2.18 unsigned int timeSinceInitialization
- 7.4.2.19 fc2TimeStamp timeStamp

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.5 fc2Config Struct Reference

Configuration for a camera.

#### **Data Fields**

• unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

· unsigned int numImageNotifications

Number of notifications per image.

· unsigned int minNumImageNotifications

Minimum number of notifications needed for the current image settings on the camera.

int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

• fc2GrabMode grabMode

Grab mode for the camera.

· BOOL highPerformanceRetrieveBuffer

This parameter enables RetrieveBuffer to run in high performance mode.

fc2BusSpeed isochBusSpeed

Isochronous bus speed.

· fc2BusSpeed asyncBusSpeed

Asynchronous bus speed.

· fc2BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

• unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

· unsigned int registerTimeout

Register read/write timeout value, in microseconds.

• unsigned int reserved [16]

Reserved for future use.

## 7.5.1 Detailed Description

Configuration for a camera.

These options are options that are generally should be set before starting isochronous transfer.

#### 7.5.2 Field Documentation

## 7.5.2.1 fc2BusSpeed asyncBusSpeed

Asynchronous bus speed.

#### 7.5.2.2 fc2BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

#### 7.5.2.3 fc2GrabMode grabMode

Grab mode for the camera.

The default is DROP\_FRAMES.

## 7.5.2.4 int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

#### 7.5.2.5 BOOL highPerformanceRetrieveBuffer

This parameter enables RetrieveBuffer to run in high performance mode.

This means that any interaction with the camera, other than grabbing the image is disabled. Currently Retrieve buffer reads registers on the camera to determine which embedded image information settings have been enabled, and it reads what the bayer tile is currently set to. When High Performance mode is on, these reads are disabled. This means that any changes to the Bayer Tile or to the Embedded image info after StartCapture() will not be tracked when made using direct register writes. If the corresponding SetEmbededImageInfo() and GetEmbededImageInfo() calls are used then the changes will be appropriately reflected. This also means that changes to embedded image info from other processes will not be updated either.

#### 7.5.2.6 fc2BusSpeed isochBusSpeed

Isochronous bus speed.

#### 7.5.2.7 unsigned int minNumImageNotifications

Minimum number of notifications needed for the current image settings on the camera. Read-only value.

#### 7.5.2.8 unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

#### 7.5.2.9 unsigned int numImageNotifications

Number of notifications per image.

This value should only be set after the image settings to be used is set to the camera. The default number of notifications is 1.

There are 4 general scenarios:

- 1 notification End of image
- · 2 notifications After first packet and end of image
- 3 notifications After first packet, middle of image, end of image
- x notifications After first packet, (x -2) spread evenly, end of image

Specifying zero for the number of notifications will be ignored (the current value will not be modified).

Note that the event numbers start at 0. Ex. when 3 notifications are used, the three events will be 0, 1 and 2.

#### 7.5.2.10 unsigned int registerTimeout

Register read/write timeout value, in microseconds.

The default value is dependent on the interface type.

#### 7.5.2.11 unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library. The default value is 0.

#### 7.5.2.12 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.6 fc2ConfigROM Struct Reference

Camera configuration ROM.

## **Data Fields**

unsigned int nodeVendorld

Vendor ID of a node.

• unsigned int chipIdHi

Chip ID (high part).

• unsigned int chipIdLo

Chip ID (low part).

unsigned int unitSpecId

Unit Spec ID, usually 0xa02d.

· unsigned int unitSWVer

Unit software version.

unsigned int unitSubSWVer

Unit sub software version.

unsigned int vendorUniqueInfo 0

Vendor unique info 0.

• unsigned int vendorUniqueInfo\_1

Vendor unique info 1.

unsigned int vendorUniqueInfo\_2

Vendor unique info 2.

• unsigned int vendorUniqueInfo\_3

Vendor unique info 3.

• char pszKeyword [MAX\_STRING\_LENGTH]

Keyword.

• unsigned int reserved [16]

Reserved for future use.

#### 7.6.1 Detailed Description

Camera configuration ROM.

## 7.6.2 Field Documentation

7.6.2.1 unsigned int chipIdHi

Chip ID (high part).

7.6.2.2 unsigned int chipIdLo

Chip ID (low part).

7.6.2.3 unsigned int nodeVendorld

Vendor ID of a node.

7.6.2.4 char pszKeyword[MAX\_STRING\_LENGTH]

Keyword.

7.6.2.5 unsigned int reserved[16]

Reserved for future use.

7.6.2.6 unsigned int unitSpecId

Unit Spec ID, usually 0xa02d.

7.6.2.7 unsigned int unitSubSWVer


Unit sub software version.

7.6.2.8	unsigned int unitSWVer	
Unit software version.		
7.6.2.9	unsigned int vendorUniqueInfo_0	
Vendor	unique info 0.	
7.6.2.10	unsigned int vendorUniqueInfo_1	
Vendor	unique info 1.	
7.6.2.11	unsigned int vendorUniqueInfo_2	
Vendor	unique info 2.	
7.6.2.12	unsigned int vendorUniqueInfo_3	
Vendor	unique info 3.	
The do	cumentation for this struct was generated from the following file:	
• F	FlyCapture2Defs_C.h	

fc2EmbeddedImageInfo Struct Reference

Properties of the possible embedded image information.

Collaboration diagram for fc2EmbeddedImageInfo:



## **Data Fields**

- fc2EmbeddedImageInfoProperty timestamp
- fc2EmbeddedImageInfoProperty gain
- fc2EmbeddedImageInfoProperty shutter
- fc2EmbeddedImageInfoProperty brightness
- fc2EmbeddedImageInfoProperty exposure
- fc2EmbeddedImageInfoProperty whiteBalance
- $\bullet \ \ fc 2 Embedded Image Info Property \ frame Counter \\$
- fc2EmbeddedImageInfoProperty strobePattern
- fc2EmbeddedImageInfoProperty GPIOPinState
- fc2EmbeddedImageInfoProperty ROIPosition

## 7.7.1 Detailed Description

Properties of the possible embedded image information.

- 7.7.2 Field Documentation
- 7.7.2.1 fc2EmbeddedImageInfoProperty brightness
- 7.7.2.2 fc2EmbeddedImageInfoProperty exposure
- 7.7.2.3 fc2EmbeddedImageInfoProperty frameCounter
- 7.7.2.4 fc2EmbeddedImageInfoProperty gain
- 7.7.2.5 fc2EmbeddedImageInfoProperty GPIOPinState
- 7.7.2.6 fc2EmbeddedImageInfoProperty ROIPosition
- 7.7.2.7 fc2EmbeddedImageInfoProperty shutter
- 7.7.2.8 fc2EmbeddedImageInfoProperty strobePattern
- 7.7.2.9 fc2EmbeddedImageInfoProperty timestamp
- 7.7.2.10 fc2EmbeddedImageInfoProperty whiteBalance

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.8 fc2EmbeddedImageInfoProperty Struct Reference

Properties of a single embedded image info property.

#### **Data Fields**

- · BOOL available
  - Whether this property is available.
- BOOL onOff

Whether this property is on or off.

#### 7.8.1 Detailed Description

Properties of a single embedded image info property.

## 7.8.2 Field Documentation

#### 7.8.2.1 BOOL available

Whether this property is available.

#### 7.8.2.2 BOOL on Off

Whether this property is on or off.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.9 fc2EventCallbackData Struct Reference

#### **Data Fields**

void \* EventUserData

Pointer to the user-supplied data struct.

• size\_t EventUserDataSize

Size of the user data supplied to the RegisterEvent() function.

const char \* EventName

The event name used to register the event.

• unsigned long long EventID

The device register which EventName maps to.

unsigned long long EventTimestamp

Timestamp indicated the time (as reported by the camera) at which the camera exposure operation completed.

void \* EventData

A pointer to additional data pertaining to the event which just trigger the callback function.

size\_t EventDataSize

The size of the structure pointed to by EventData.

## 7.9.1 Field Documentation

### 7.9.1.1 void\* EventData

A pointer to additional data pertaining to the event which just trigger the callback function

The data may be of difference sizes or may not even be allocated, depending on the type of event which triggered the callback.

#### 7.9.1.2 size\_t EventDataSize

The size of the structure pointed to by EventData.

This value should be checked, especially if there are events which can trigger variable-length event data to be returned to the user when the callback function is issued.

#### 7.9.1.3 unsigned long long EventID

The device register which EventName maps to.

Provides an alternate means of indexing into different event types.

#### 7.9.1.4 const char\* EventName

The event name used to register the event.

Provided so the user knows which event triggered the callback.

#### 7.9.1.5 unsigned long long EventTimestamp

Timestamp indicated the time (as reported by the camera) at which the camera exposure operation completed.

This can be compared with image timestamps if there is a need to map event timestamps to specific images, if applicable.

#### 7.9.1.6 void\* EventUserData

Pointer to the user-supplied data struct.

#### 7.9.1.7 size\_t EventUserDataSize

Size of the user data supplied to the RegisterEvent() function.

The documentation for this struct was generated from the following file:

FlyCapture2Defs\_C.h

## 7.10 fc2EventOptions Struct Reference

Options for enabling device event registration.

### **Data Fields**

fc2CameraEventCallback EventCallbackFcn

Callback function pointer.

• const char \* EventName

Event name to register.

const void \* EventUserData

Pointer to callback data to be passed to the callback function.

size\_t EventUserDataSize

Size of the underlying struct passed as eventCallbackData for sanity checks.

#### 7.10.1 Detailed Description

Options for enabling device event registration.

#### 7.10.2 Field Documentation

## 7.10.2.1 fc2CameraEventCallback EventCallbackFcn

Callback function pointer.

#### 7.10.2.2 const char\* EventName

Event name to register.

#### 7.10.2.3 const void\* EventUserData

Pointer to callback data to be passed to the callback function.

#### 7.10.2.4 size\_t EventUserDataSize

Size of the underlying struct passed as eventCallbackData for sanity checks.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.11 fc2Format7ImageSettings Struct Reference

Format 7 image settings.

#### **Data Fields**

fc2Mode mode

Format 7 mode.

unsigned int offsetX

Horizontal image offset.

unsigned int offsetY

Vertical image offset.

· unsigned int width

Width of image.

· unsigned int height

Height of image.

· fc2PixelFormat pixelFormat

Pixel format of image.

• unsigned int reserved [8]

Reserved for future use.

## 7.11.1 Detailed Description

Format 7 image settings.

#### 7.11.2 Field Documentation

7.11.2.1 unsigned int height

Height of image.

### 7.11.2.2 fc2Mode mode

Format 7 mode.

7.11.2.3 unsigned int offsetX

Horizontal image offset.

7.11.2.4 unsigned int offsetY

Vertical image offset.

## 7.11.2.5 fc2PixelFormat pixelFormat

Pixel format of image.

7.11.2.6 unsigned int reserved[8]

Reserved for future use.

#### 7.11.2.7 unsigned int width

Width of image.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.12 fc2Format7Info Struct Reference

Format 7 information for a single mode.

#### **Data Fields**

fc2Mode mode

Format 7 mode.

• unsigned int maxWidth

Maximum image width.

unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

· unsigned int offsetVStepSize

Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

• unsigned int imageVStepSize

Vertical step size for the image.

· unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

· unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

• unsigned int packetSize

Current packet size in bytes.

• unsigned int minPacketSize

Minimum packet size in bytes for current mode.

· unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

· float percentage

Current packet size as a percentage of maximum packet size.

• unsigned int reserved [16]

Reserved for future use.

# 7.12.1 Detailed Description

Format 7 information for a single mode.

# 7.12.2 Field Documentation

### 7.12.2.1 unsigned int imageHStepSize

Horizontal step size for the image.

### 7.12.2.2 unsigned int imageVStepSize

Vertical step size for the image.

### 7.12.2.3 unsigned int maxHeight

Maximum image height.

### 7.12.2.4 unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

# 7.12.2.5 unsigned int maxWidth

Maximum image width.

# 7.12.2.6 unsigned int minPacketSize

Minimum packet size in bytes for current mode.

### 7.12.2.7 fc2Mode mode

Format 7 mode.

# 7.12.2.8 unsigned int offsetHStepSize

Horizontal step size for the offset.

# 7.12.2.9 unsigned int offsetVStepSize

Vertical step size for the offset.

7.12.2.10 unsigned int packetSize

Current packet size in bytes.

7.12.2.11 float percentage

Current packet size as a percentage of maximum packet size.

7.12.2.12 unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

7.12.2.13 unsigned int reserved[16]

Reserved for future use.

7.12.2.14 unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.13 fc2Format7PacketInfo Struct Reference

Format 7 packet information.

#### **Data Fields**

- · unsigned int recommendedBytesPerPacket
  - Recommended bytes per packet.
- unsigned int maxBytesPerPacket

Maximum bytes per packet.

- unsigned int unitBytesPerPacket
  - Minimum bytes per packet.
- unsigned int reserved [8]

Reserved for future use.

# 7.13.1 Detailed Description

Format 7 packet information.

# 7.13.2 Field Documentation

#### 7.13.2.1 unsigned int maxBytesPerPacket

Maximum bytes per packet.

#### 7.13.2.2 unsigned int recommendedBytesPerPacket

Recommended bytes per packet.

### 7.13.2.3 unsigned int reserved[8]

Reserved for future use.

# 7.13.2.4 unsigned int unitBytesPerPacket

Minimum bytes per packet.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.14 fc2GigEConfig Struct Reference

Configuration for a GigE camera.

## **Data Fields**

BOOL enablePacketResend

Turn on/off packet resend functionality.

• unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

• unsigned int registerTimeout

Register read/write timeout value, in microseconds.

• unsigned int reserved [8]

### 7.14.1 Detailed Description

Configuration for a GigE camera.

These options are options that are generally should be set before starting isochronous transfer.

### 7.14.2 Field Documentation

#### 7.14.2.1 BOOL enablePacketResend

Turn on/off packet resend functionality.

### 7.14.2.2 unsigned int registerTimeout

Register read/write timeout value, in microseconds.

The default value is dependent on the interface type.

### 7.14.2.3 unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library. The default value is 0.

### 7.14.2.4 unsigned int reserved[8]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.15 fc2GigEImageSettings Struct Reference

Image settings for a GigE camera.

### **Data Fields**

unsigned int offsetX

Horizontal image offset.

unsigned int offsetY

Vertical image offset.

· unsigned int width

Width of image.

· unsigned int height

Height of image.

• fc2PixelFormat pixelFormat

Pixel format of image.

• unsigned int reserved [8]

Reserved for future use.

# 7.15.1 Detailed Description

Image settings for a GigE camera.

### 7.15.2 Field Documentation

7.15.2.1 unsigned int height

Height of image.

7.15.2.2 unsigned int offsetX

Horizontal image offset.

7.15.2.3 unsigned int offsetY

Vertical image offset.

### 7.15.2.4 fc2PixelFormat pixelFormat

Pixel format of image.

7.15.2.5 unsigned int reserved[8]

Reserved for future use.

7.15.2.6 unsigned int width

Width of image.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.16 fc2GigElmageSettingsInfo Struct Reference

Format 7 information for a single mode.

## **Data Fields**

unsigned int maxWidth
 Maximum image width.

· unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

unsigned int offsetVStepSize

Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

unsigned int imageVStepSize

Vertical step size for the image.

· unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

· unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

• unsigned int reserved [16]

Reserved for future use.

# 7.16.1 Detailed Description

Format 7 information for a single mode.

# 7.16.2 Field Documentation

7.16.2.1 unsigned int imageHStepSize

Horizontal step size for the image.

7.16.2.2 unsigned int imageVStepSize

Vertical step size for the image.

7.16.2.3 unsigned int maxHeight

Maximum image height.

7.16.2.4 unsigned int maxWidth

Maximum image width.

7.16.2.5 unsigned int offsetHStepSize

Horizontal step size for the offset.

### 7.16.2.6 unsigned int offsetVStepSize

Vertical step size for the offset.

# 7.16.2.7 unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

### 7.16.2.8 unsigned int reserved[16]

Reserved for future use.

#### 7.16.2.9 unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.17 fc2GigEProperty Struct Reference

A GigE property.

#### **Data Fields**

• fc2GigEPropertyType propType

The type of property.

• BOOL isReadable

Whether the property is readable.

BOOL isWritable

Whether the property is writable.

· unsigned int min

Minimum value.

unsigned int max

Maximum value.

• unsigned int value

Current value.

• unsigned int reserved [8]

# 7.17.1 Detailed Description

A GigE property.

### 7.17.2 Field Documentation

### 7.17.2.1 BOOL is Readable

Whether the property is readable.

If this is false, then no other value in this structure is valid.

#### 7.17.2.2 BOOL is Writable

Whether the property is writable.

### 7.17.2.3 unsigned int max

Maximum value.

### 7.17.2.4 unsigned int min

Minimum value.

# 7.17.2.5 fc2GigEPropertyType propType

The type of property.

### 7.17.2.6 unsigned int reserved[8]

# 7.17.2.7 unsigned int value

Current value.


The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.18 fc2GigEStreamChannel Struct Reference

Information about a single GigE stream channel.

Collaboration diagram for fc2GigEStreamChannel:



# **Data Fields**

· unsigned int networkInterfaceIndex

Network interface index used (or to use).

unsigned int hostPort

Host port on the PC where the camera will send the data stream.

• BOOL doNotFragment

Disable IP fragmentation of packets.

• unsigned int packetSize

Packet size, in bytes.

unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

• fc2IPAddress destinationIpAddress

Destination IP address.

• unsigned int sourcePort

Source UDP port of the stream channel.

• unsigned int reserved [8]

### 7.18.1 Detailed Description

Information about a single GigE stream channel.

#### 7.18.2 Field Documentation

# 7.18.2.1 fc2IPAddress destinationIpAddress

Destination IP address.

It can be a multicast or unicast address.

### 7.18.2.2 BOOL doNotFragment

Disable IP fragmentation of packets.

### 7.18.2.3 unsigned int hostPort

Host port on the PC where the camera will send the data stream.

#### 7.18.2.4 unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

# 7.18.2.5 unsigned int networkInterfaceIndex

Network interface index used (or to use).

### 7.18.2.6 unsigned int packetSize

Packet size, in bytes.

# 7.18.2.7 unsigned int reserved[8]

### 7.18.2.8 unsigned int sourcePort

Source UDP port of the stream channel.

Read only.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.19 fc2H264Option Struct Reference

Options for saving H264 files.

#### **Data Fields**

float frameRate

Frame rate of the stream.

· unsigned int width

Width of source image.

unsigned int height

Height of source image.

· unsigned int bitrate

Bitrate to encode at.

unsigned int reserved [256]

Reserved for future use.

# 7.19.1 Detailed Description

Options for saving H264 files.

#### 7.19.2 Field Documentation

7.19.2.1 unsigned int bitrate

Bitrate to encode at.

#### 7.19.2.2 float frameRate

Frame rate of the stream.

7.19.2.3 unsigned int height

Height of source image.

7.19.2.4 unsigned int reserved[256]

Reserved for future use.

7.19.2.5 unsigned int width

Width of source image.

The documentation for this struct was generated from the following file:

• FlyCapture2VideoDefs\_C.h

# 7.20 fc2Image Struct Reference

## **Data Fields**

· unsigned int rows

- · unsigned int cols
- · unsigned int stride
- unsigned char \* pData
- · unsigned int dataSize
- unsigned int receivedDataSize
- · fc2PixelFormat format
- fc2BayerTileFormat bayerFormat
- fc2lmagelmpl imagelmpl

#### 7.20.1 Field Documentation

- 7.20.1.1 fc2BayerTileFormat bayerFormat
- 7.20.1.2 unsigned int cols
- 7.20.1.3 unsigned int dataSize
- 7.20.1.4 fc2PixelFormat format
- 7.20.1.5 fc2lmagelmpl imagelmpl
- 7.20.1.6 unsigned char\* pData
- 7.20.1.7 unsigned int receivedDataSize
- 7.20.1.8 unsigned int rows
- 7.20.1.9 unsigned int stride

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.21 fc2ImageMetadata Struct Reference

Metadata related to an image.

### **Data Fields**

- unsigned int embeddedTimeStamp
  - Embedded timestamp.
- unsigned int embeddedGain
  - Embedded gain.
- · unsigned int embeddedShutter

Embedded shutter.

• unsigned int embeddedBrightness

Embedded brightness.

• unsigned int embeddedExposure

Embedded exposure.

• unsigned int embeddedWhiteBalance

Embedded white balance.

• unsigned int embeddedFrameCounter

Embedded frame counter.

• unsigned int embeddedStrobePattern

Embedded strobe pattern.

• unsigned int embeddedGPIOPinState

Embedded GPIO pin state.

unsigned int embeddedROIPosition

Embedded ROI position.

• unsigned int reserved [31]

Reserved for future use.

# 7.21.1 Detailed Description

Metadata related to an image.

## 7.21.2 Field Documentation

# 7.21.2.1 unsigned int embeddedBrightness

Embedded brightness.

7.21.2.2 unsigned int embeddedExposure

Embedded exposure.

7.21.2.3 unsigned int embeddedFrameCounter

Embedded frame counter.

7.21.2.4 unsigned int embeddedGain

Embedded gain.

7.21.2.5 unsigned int embeddedGPIOPinState

Embedded GPIO pin state.

7.21.2.6 unsigned int embeddedROIPosition

Embedded ROI position.

7.21.2.7 unsigned int embeddedShutter

Embedded shutter.

7.21.2.8 unsigned int embeddedStrobePattern

Embedded strobe pattern.

7.21.2.9 unsigned int embeddedTimeStamp

Embedded timestamp.

7.21.2.10 unsigned int embeddedWhiteBalance

Embedded white balance.

7.21.2.11 unsigned int reserved[31]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.22 fc2InternalContext Struct Reference

#### **Data Fields**

- FlyCapture2::BusManager \* pBusMgr
- FlyCapture2::CameraBase \* pCamera

# 7.22.1 Field Documentation

7.22.1.1 FlyCapture2::BusManager\* pBusMgr

7.22.1.2 FlyCapture2::CameraBase\* pCamera

The documentation for this struct was generated from the following file:

• FlyCapture2Internal\_C.h

# 7.23 fc2InternalGuiContext Struct Reference

### **Data Fields**

- FlyCapture2::CameraSelectionDlg \* pCameraSelectionDlg
- FlyCapture2::CameraControlDlg \* pCameraControlDlg

### 7.23.1 Field Documentation


- 7.23.1.1 FlyCapture2::CameraControlDlg\* pCameraControlDlg
- 7.23.1.2 FlyCapture2::CameraSelectionDlg\* pCameraSelectionDlg

The documentation for this struct was generated from the following file:

• FlyCapture2Internal\_C.h

# 7.24 fc2InternalImageCallback Struct Reference

Collaboration diagram for fc2InternalImageCallback:



### **Data Fields**

- fc2ImageEventCallback pCallback
- void \* pCallbackData

## 7.24.1 Field Documentation

### 7.24.1.1 fc2ImageEventCallback pCallback

#### 7.24.1.2 void\* pCallbackData

The documentation for this struct was generated from the following file:

• FlyCapture2Internal\_C.h

# 7.25 fc2IPAddress Struct Reference

IPv4 address.

### **Data Fields**

• unsigned char octets [4]

# 7.25.1 Detailed Description

IPv4 address.

### 7.25.2 Field Documentation

### 7.25.2.1 unsigned char octets[4]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.26 fc2JPEGOption Struct Reference

Options for saving JPEG image.

### **Data Fields**

• BOOL progressive

Whether to save as a progressive JPEG file.

· unsigned int quality

JPEG image quality in range (0-100).

• unsigned int reserved [16]

Reserved for future use.

# 7.26.1 Detailed Description

Options for saving JPEG image.

### 7.26.2 Field Documentation

### 7.26.2.1 BOOL progressive

Whether to save as a progressive JPEG file.

# 7.26.2.2 unsigned int quality

JPEG image quality in range (0-100).

- 100 Superb quality.
- 75 Good quality.
- 50 Normal quality.
- 10 Poor quality.

### 7.26.2.3 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.27 fc2JPG2Option Struct Reference

Options for saving JPEG2000 image.

#### **Data Fields**

· unsigned int quality

JPEG saving quality in range (1-512).

• unsigned int reserved [16]

Reserved for future use.

# 7.27.1 Detailed Description

Options for saving JPEG2000 image.

#### 7.27.2 Field Documentation

7.27.2.1 unsigned int quality

JPEG saving quality in range (1-512).

#### 7.27.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.28 fc2LUTData Struct Reference

Information about the camera's look up table.

# **Data Fields**

· BOOL supported

Flag indicating if LUT is supported.

· BOOL enabled

Flag indicating if LUT is enabled.

• unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

• unsigned int numChannels

The number of LUT channels per bank available.

• unsigned int inputBitDepth

The input bit depth of the LUT.

• unsigned int outputBitDepth

The output bit depth of the LUT.

• unsigned int numEntries

The number of entries in the LUT.

• unsigned int reserved [8]

Reserved for future use.

# 7.28.1 Detailed Description

Information about the camera's look up table.

7.28.2 Field Documentation

7.28.2.1 BOOL enabled

Flag indicating if LUT is enabled.

7.28.2.2 unsigned int inputBitDepth

The input bit depth of the LUT.

7.28.2.3 unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

7.28.2.4 unsigned int numChannels

The number of LUT channels per bank available.

7.28.2.5 unsigned int numEntries

The number of entries in the LUT.

7.28.2.6 unsigned int outputBitDepth

The output bit depth of the LUT.

7.28.2.7 unsigned int reserved[8]

Reserved for future use.

7.28.2.8 BOOL supported

Flag indicating if LUT is supported.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.29 fc2MACAddress Struct Reference

MAC address.

# **Data Fields**

• unsigned char octets [6]

# 7.29.1 Detailed Description

MAC address.

### 7.29.2 Field Documentation

# 7.29.2.1 unsigned char octets[6]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.30 fc2MJPGOption Struct Reference

Options for saving MJPG files.

# **Data Fields**

- float frameRate
  - Frame rate of the stream.
- · unsigned int quality

Image quality (1-100)

• unsigned int reserved [256]

# 7.30.1 Detailed Description

Options for saving MJPG files.

#### 7.30.2 Field Documentation

7.30.2.1 float frameRate

Frame rate of the stream.

7.30.2.2 unsigned int quality

Image quality (1-100)

### 7.30.2.3 unsigned int reserved[256]

The documentation for this struct was generated from the following file:

• FlyCapture2VideoDefs\_C.h

# 7.31 fc2PGMOption Struct Reference

Options for saving PGM images.

# **Data Fields**

• BOOL binaryFile

Whether to save the PPM as a binary file.

• unsigned int reserved [16]

Reserved for future use.

# 7.31.1 Detailed Description

Options for saving PGM images.

#### 7.31.2 Field Documentation

# 7.31.2.1 BOOL binaryFile

Whether to save the PPM as a binary file.

# 7.31.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.32 fc2PGRGuid Struct Reference

A GUID to the camera.

### **Data Fields**

• unsigned int value [4]

### 7.32.1 Detailed Description

A GUID to the camera.

It is used to uniquely identify a camera.

#### 7.32.2 Field Documentation

#### 7.32.2.1 unsigned int value[4]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.33 fc2PNGOption Struct Reference

Options for saving PNG images.

#### **Data Fields**

· BOOL interlaced

Whether to save the PNG as interlaced.

• unsigned int compressionLevel

Compression level (0-9).

• unsigned int reserved [16]

Reserved for future use.

# 7.33.1 Detailed Description

Options for saving PNG images.

#### 7.33.2 Field Documentation

# 7.33.2.1 unsigned int compressionLevel

Compression level (0-9).

0 is no compression, 9 is best compression.

#### 7.33.2.2 BOOL interlaced

Whether to save the PNG as interlaced.

#### 7.33.2.3 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.34 fc2PPMOption Struct Reference

Options for saving PPM images.

### **Data Fields**

BOOL binaryFile

Whether to save the PPM as a binary file.

• unsigned int reserved [16]

Reserved for future use.

# 7.34.1 Detailed Description

Options for saving PPM images.

# 7.34.2 Field Documentation

### 7.34.2.1 BOOL binaryFile

Whether to save the PPM as a binary file.

## 7.34.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.35 fc2StrobeControl Struct Reference

A camera strobe.

# **Data Fields**

• unsigned int source

Source value.

• BOOL onOff

Flag controlling on/off.

· unsigned int polarity

Signal polarity.

float delay

Signal delay (in ms).

float duration

Signal duration (in ms).

• unsigned int reserved [8]

Reserved for future use.

# 7.35.1 Detailed Description

A camera strobe.

## 7.35.2 Field Documentation

7.35.2.1 float delay

Signal delay (in ms).

7.35.2.2 float duration

Signal duration (in ms).

7.35.2.3 BOOL onOff

Flag controlling on/off.

7.35.2.4 unsigned int polarity

Signal polarity.

7.35.2.5 unsigned int reserved[8]

Reserved for future use.

#### 7.35.2.6 unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.36 fc2Strobelnfo Struct Reference

A camera strobe property.

# **Data Fields**

· unsigned int source

Source value.

BOOL present

Presence of strobe.

• BOOL readOutSupported

Flag indicating if strobe value can be read out.

• BOOL onOffSupported

Flag indicating if on/off is supported.

• BOOL polaritySupported

Flag indicating if polarity is supported.

float minValue

Minimum value.

float maxValue

Maximum value.

• unsigned int reserved [8]

Reserved for future use.

# 7.36.1 Detailed Description

A camera strobe property.

# 7.36.2 Field Documentation

#### 7.36.2.1 float maxValue

Maximum value.

7.36.2.2 float minValue

Minimum value.

7.36.2.3 BOOL on Off Supported

Flag indicating if on/off is supported.

7.36.2.4 BOOL polaritySupported

Flag indicating if polarity is supported.

7.36.2.5 BOOL present

Presence of strobe.

7.36.2.6 BOOL readOutSupported

Flag indicating if strobe value can be read out.

7.36.2.7 unsigned int reserved[8]

Reserved for future use.

7.36.2.8 unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.37 fc2SystemInfo Struct Reference

Description of the system.

#### **Data Fields**

• fc2OSType osType

Operating system type as described by OSType.

• char osDescription [MAX\_STRING\_LENGTH]

Detailed description of the operating system.

fc2ByteOrder byteOrder

Byte order of the system.

size\_t sysMemSize

Amount of memory available on the system.

char cpuDescription [MAX\_STRING\_LENGTH]

Detailed description of the CPU.

size\_t numCpuCores

Number of cores on all CPUs on the system.

char driverList [MAX\_STRING\_LENGTH]

List of drivers used.

• char libraryList [MAX\_STRING\_LENGTH]

List of libraries used.

• char gpuDescription [MAX\_STRING\_LENGTH]

Detailed description of the GPU.

• size\_t screenWidth

Screen resolution width in pixels.

• size\_t screenHeight

Screen resolution height in pixels.

• unsigned int reserved [16]

Reserved for future use.

# 7.37.1 Detailed Description

Description of the system.

#### 7.37.2 Field Documentation

### 7.37.2.1 fc2ByteOrder byteOrder

Byte order of the system.

# 7.37.2.2 char cpuDescription[MAX\_STRING\_LENGTH]

Detailed description of the CPU.

### 7.37.2.3 char driverList[MAX\_STRING\_LENGTH]

List of drivers used.

# 7.37.2.4 char gpuDescription[MAX\_STRING\_LENGTH]

Detailed description of the GPU.

7.37.2.5 char libraryList[MAX\_STRING\_LENGTH]

List of libraries used.

7.37.2.6 size\_t numCpuCores

Number of cores on all CPUs on the system.

7.37.2.7 char osDescription[MAX\_STRING\_LENGTH]

Detailed description of the operating system.

7.37.2.8 fc2OSType osType

Operating system type as described by OSType.

7.37.2.9 unsigned int reserved[16]

Reserved for future use.

7.37.2.10 size\_t screenHeight

Screen resolution height in pixels.

7.37.2.11 size\_t screenWidth

Screen resolution width in pixels.

7.37.2.12 size\_t sysMemSize

Amount of memory available on the system.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.38 fc2TIFFOption Struct Reference

Options for saving TIFF images.

### **Data Fields**

fc2TIFFCompressionMethod compression

Compression method to use for encoding TIFF images.

• unsigned int reserved [16]

Reserved for future use.

# 7.38.1 Detailed Description

Options for saving TIFF images.

### 7.38.2 Field Documentation

### 7.38.2.1 fc2TIFFCompressionMethod compression

Compression method to use for encoding TIFF images.

#### 7.38.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.39 fc2TimeStamp Struct Reference

Timestamp information.

## **Data Fields**

• long long seconds

Seconds.

• unsigned int microSeconds

Microseconds.

• unsigned int cycleSeconds

1394 cycle time seconds.

unsigned int cycleCount

1394 cycle time count.

unsigned int cycleOffset

1394 cycle time offset.

• unsigned int reserved [8]

Reserved for future use.

# 7.39.1 Detailed Description

Timestamp information.

# 7.39.2 Field Documentation

7.39.2.1 unsigned int cycleCount

1394 cycle time count.

7.39.2.2 unsigned int cycleOffset

1394 cycle time offset.

7.39.2.3 unsigned int cycleSeconds

1394 cycle time seconds.

7.39.2.4 unsigned int microSeconds

Microseconds.

7.39.2.5 unsigned int reserved[8]

Reserved for future use.

7.39.2.6 long long seconds

Seconds.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.40 fc2TriggerDelay Struct Reference

A specific camera property.

## **Data Fields**

fc2PropertyType type

Property info type.

BOOL present

Flag indicating if the property is present.

BOOL absControl

Flag controlling absolute mode (real world units) or non-absolute mode (camera internal units).

BOOL onePush

Flag controlling one push.

BOOL onOff

Flag controlling on/off.

• BOOL autoManualMode

Flag controlling auto.

· unsigned int valueA

Value A (integer).

unsigned int valueB

Value B (integer).

• float absValue

Floating point value.

• unsigned int reserved [8]

Reserved for future use.

# 7.40.1 Detailed Description

A specific camera property.

For example, to set the gain to 12dB, set the following values:

- type GAIN
- absControl true
- onePush false
- onOff true
- autoManualMode false
- absValue 12.0

### 7.40.2 Field Documentation

### 7.40.2.1 BOOL absControl

Flag controlling absolute mode (real world units) or non-absolute mode (camera internal units).

7.40.2.2 float absValue

Floating point value.

Used to configure properties in absolute mode.

7.40.2.3 BOOL autoManualMode

Flag controlling auto.

7.40.2.4 BOOL onePush

Flag controlling one push.

7.40.2.5 BOOL onOff

Flag controlling on/off.

7.40.2.6 BOOL present

Flag indicating if the property is present.

7.40.2.7 unsigned int reserved[8]

Reserved for future use.

7.40.2.8 fc2PropertyType type

Property info type.

7.40.2.9 unsigned int valueA

Value A (integer).

Used to configure properties in non-absolute mode.

7.40.2.10 unsigned int valueB

Value B (integer).

For white balance, value B applies to the blue value and value A applies to the red value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.41 fc2TriggerDelayInfo Struct Reference

Information about a specific camera property.

### **Data Fields**

fc2PropertyType type

Property info type.

BOOL present

Flag indicating if the property is present.

BOOL autoSupported

Flag indicating if auto is supported.

· BOOL manualSupported

Flag indicating if manual is supported.

· BOOL onOffSupported

Flag indicating if on/off is supported.

BOOL onePushSupported

Flag indicating if one push is supported.

• BOOL absValSupported

Flag indicating if absolute mode is supported.

• BOOL readOutSupported

Flag indicating if property value can be read out.

unsigned int min

Minimum value (as an integer).

· unsigned int max

Maximum value (as an integer).

• float absMin

Minimum value (as a floating point value).

float absMax

Maximum value (as a floating point value).

• char pUnits [MAX\_STRING\_LENGTH]

Textual description of units.

char pUnitAbbr [MAX\_STRING\_LENGTH]

Abbreviated textual description of units.

• unsigned int reserved [8]

Reserved for future use.

# 7.41.1 Detailed Description

Information about a specific camera property.

This structure is also also used as the TriggerDelayInfo structure.

### 7.41.2 Field Documentation

#### 7.41.2.1 float absMax

Maximum value (as a floating point value).

#### 7.41.2.2 float absMin

Minimum value (as a floating point value).

# 7.41.2.3 BOOL absValSupported

Flag indicating if absolute mode is supported.

# 7.41.2.4 BOOL autoSupported

Flag indicating if auto is supported.

### 7.41.2.5 BOOL manual Supported

Flag indicating if manual is supported.

### 7.41.2.6 unsigned int max

Maximum value (as an integer).

#### 7.41.2.7 unsigned int min

Minimum value (as an integer).

# 7.41.2.8 BOOL onePushSupported

Flag indicating if one push is supported.

# 7.41.2.9 BOOL onOffSupported

Flag indicating if on/off is supported.

# 7.41.2.10 BOOL present

Flag indicating if the property is present.

### 7.41.2.11 char pUnitAbbr[MAX\_STRING\_LENGTH]

Abbreviated textual description of units.

### 7.41.2.12 char pUnits[MAX\_STRING\_LENGTH]

Textual description of units.

# 7.41.2.13 BOOL readOutSupported

Flag indicating if property value can be read out.

### 7.41.2.14 unsigned int reserved[8]

Reserved for future use.

### 7.41.2.15 fc2PropertyType type

Property info type.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.42 fc2TriggerMode Struct Reference

A camera trigger.

#### **Data Fields**

• BOOL onOff

Flag controlling on/off.

· unsigned int polarity

Polarity value.

• unsigned int source

Source value.

· unsigned int mode

Mode value.

• unsigned int parameter

Parameter value.

• unsigned int reserved [8]

Reserved for future use.

# 7.42.1 Detailed Description

A camera trigger.

### 7.42.2 Field Documentation

7.42.2.1 unsigned int mode

Mode value.

7.42.2.2 BOOL onOff

Flag controlling on/off.

7.42.2.3 unsigned int parameter

Parameter value.

7.42.2.4 unsigned int polarity

Polarity value.

7.42.2.5 unsigned int reserved[8]

Reserved for future use.

7.42.2.6 unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

# 7.43 fc2TriggerModeInfo Struct Reference

Information about a camera trigger property.

## **Data Fields**

BOOL present

Presence of trigger mode.

BOOL readOutSupported

Flag indicating if trigger value can be read out.

· BOOL onOffSupported

Flag indicating if on/off is supported.

BOOL polaritySupported

Flag indicating if polarity is supported.

• BOOL valueReadable

Flag indicating if the value is readable.

unsigned int sourceMask

Source mask.

• BOOL softwareTriggerSupported

Flag indicating if software trigger is supported.

• unsigned int modeMask

Mode mask.

• unsigned int reserved [8]

Reserved for future use.

## 7.43.1 Detailed Description

Information about a camera trigger property.

## 7.43.2 Field Documentation

## 7.43.2.1 unsigned int modeMask

Mode mask.

## 7.43.2.2 BOOL on Off Supported

Flag indicating if on/off is supported.

## 7.43.2.3 BOOL polaritySupported

Flag indicating if polarity is supported.

#### 7.43.2.4 BOOL present

Presence of trigger mode.

## 7.43.2.5 BOOL readOutSupported

Flag indicating if trigger value can be read out.

#### 7.43.2.6 unsigned int reserved[8]

Reserved for future use.

#### 7.43.2.7 BOOL software Trigger Supported

Flag indicating if software trigger is supported.

## 7.43.2.8 unsigned int sourceMask

Source mask.

#### 7.43.2.9 BOOL valueReadable

Flag indicating if the value is readable.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## 7.44 fc2Version Struct Reference

The current version of the library.

## **Data Fields**

- · unsigned int major
  - Major version number.
- · unsigned int minor

Minor version number.

- · unsigned int type
  - Type version number.
- · unsigned int build

Build version number.

## 7.44.1 Detailed Description

The current version of the library.

## 7.44.2 Field Documentation

7.44.2.1 unsigned int build

Build version number.

7.44.2.2 unsigned int major

Major version number.

7.44.2.3 unsigned int minor

Minor version number.

7.44.2.4 unsigned int type

Type version number.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs\_C.h

## **Chapter 8**

## **File Documentation**

## 8.1 FlyCapture2\_C.h File Reference

#### **Functions**

- FLYCAPTURE2\_C\_API fc2Error fc2CreateContext (fc2Context \*pContext)
   Create a FC2 context for IIDC camera.
- FLYCAPTURE2\_C\_API fc2Error fc2CreateGigEContext (fc2Context \*p-Context)

Create a FC2 context for a GigE Vision camera.

- FLYCAPTURE2\_C\_API fc2Error fc2DestroyContext (fc2Context context)

  Destroy the FC2 context.
- FLYCAPTURE2\_C\_API fc2Error fc2FireBusReset (fc2Context context, fc2PGR-Guid \*pGuid)

Fire a bus reset.

FLYCAPTURE2\_C\_API fc2Error fc2GetNumOfCameras (fc2Context context, unsigned int \*pNumCameras)

Gets the number of cameras attached to the PC.

FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromIPAddress (fc2Context context, fc2IPAddress ipAddress, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a camera with the specified IPv4 address.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromIndex (fc2Context context, unsigned int index, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraFromSerialNumber (fc2Context context, unsigned int serialNumber, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraSerialNumberFromIndex (fc2-Context context, unsigned int index, unsigned int \*pSerialNumber)

Gets the serial number of the camera with the specified index.

FLYCAPTURE2\_C\_API fc2Error fc2GetInterfaceTypeFromGuid (fc2Context context, fc2PGRGuid \*pGuid, fc2InterfaceType \*pInterfaceType)

Gets the interface type associated with a PGRGuid.

FLYCAPTURE2\_C\_API fc2Error fc2GetNumOfDevices (fc2Context context, unsigned int \*pNumDevices)

Gets the number of devices.

 FLYCAPTURE2\_C\_API fc2Error fc2GetDeviceFromIndex (fc2Context context, unsigned int index, fc2PGRGuid \*pGuid)

Gets the PGRGuid for a device.

FLYCAPTURE2\_C\_API fc2Error fc2ReadPhyRegister (fc2Context context, fc2-PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int \*pValue)

Read a phy register on the specified device.

 FLYCAPTURE2\_C\_API fc2Error fc2WritePhyRegister (fc2Context context, fc2-PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)

Write a phy register on the specified device.

FLYCAPTURE2\_C\_API fc2Error fc2GetUsbLinkInfo (fc2Context context, fc2PG-RGuid guid, unsigned int \*pValue)

Read usb link info for the port that the specified device is connected to.

 FLYCAPTURE2\_C\_API fc2Error fc2GetUsbPortStatus (fc2Context context, fc2-PGRGuid guid, unsigned int \*pValue)

Read usb port status for the port that the specified device is connected to.

 FLYCAPTURE2\_C\_API fc2Error fc2GetTopology (fc2Context context, fc2-TopologyNodeContext \*pTopologyNodeContext)

Gets the topology information for the PC.

• FLYCAPTURE2\_C\_API fc2Error fc2RegisterCallback (fc2Context context, fc2-BusEventCallback enumCallback, fc2BusCallbackType callbackType, void \*p-Parameter, fc2CallbackHandle \*pCallbackHandle)

Register a callback function that will be called when the specified callback event occurs.

 FLYCAPTURE2\_C\_API fc2Error fc2UnregisterCallback (fc2Context context, fc2-CallbackHandle callbackHandle)

Unregister a callback function.

• FLYCAPTURE2\_C\_API fc2Error fc2RescanBus (fc2Context context)

Force a rescan of the buses.

FLYCAPTURE2\_C\_API fc2Error fc2ForceIPAddressToCamera (fc2Context context, fc2MACAddress macAddress, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

FLYCAPTURE2\_C\_API fc2Error fc2ForceAllIPAddressesAutomatically ()

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

FLYCAPTURE2\_C\_API fc2Error fc2ForceIPAddressAutomatically (unsigned int serialNumber)

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

 FLYCAPTURE2\_C\_API fc2Error fc2DiscoverGigECameras (fc2Context context, fc2CameraInfo \*gigECameras, unsigned int \*arraySize)

Discover all cameras connected to the network even if they reside on a different subnet.

FLYCAPTURE2\_C\_API fc2Error fc2IsCameraControlable (fc2Context context, fc2PGRGuid \*pGuid, BOOL \*pControlable)

Query whether a GigE camera is controllable.

 FLYCAPTURE2\_C\_API fc2Error fc2Connect (fc2Context context, fc2PGRGuid \*guid)

Connects the fc2Context to the camera specified by the GUID.

FLYCAPTURE2\_C\_API fc2Error fc2Disconnect (fc2Context context)

Disconnects the fc2Context from the camera.

FLYCAPTURE2 C API BOOL fc2IsConnected (fc2Context context)

Checks if the fc2Context is connected to a physical camera specified by a GUID.

 FLYCAPTURE2\_C\_API fc2Error fc2SetCallback (fc2Context context, fc2Image-EventCallback pCallbackFn, void \*pCallbackData)

Sets the callback data to be used on completion of image transfer.

FLYCAPTURE2\_C\_API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

 FLYCAPTURE2\_C\_API fc2Error fc2StartCaptureCallback (fc2Context context, fc2ImageEventCallback pCallbackFn, void \*pCallbackData)

Starts isochronous image capture.

 FLYCAPTURE2\_C\_API fc2Error fc2StartSyncCapture (unsigned int num-Cameras, fc2Context \*pContexts)

Starts synchronized isochronous image capture on multiple cameras.

 FLYCAPTURE2\_C\_API fc2Error fc2StartSyncCaptureCallback (unsigned int numCameras, fc2Context \*pContexts, fc2ImageEventCallback \*pCallbackFns, void \*\*pCallbackDataArray)

Starts synchronized isochronous image capture on multiple cameras.

 FLYCAPTURE2\_C\_API fc2Error fc2RetrieveBuffer (fc2Context context, fc2lmage \*plmage)

Retrieves the next image object containing the next image.

FLYCAPTURE2\_C\_API fc2Error fc2StopCapture (fc2Context context)

Stops isochronous image transfer and cleans up all associated resources.

 FLYCAPTURE2\_C\_API fc2Error fc2WaitForBufferEvent (fc2Context context, fc2lmage \*plmage, unsigned int eventNumber)

Retrieves the next image event containing the next part of the image.

FLYCAPTURE2\_C\_API fc2Error fc2SetUserBuffers (fc2Context context, unsigned char \*const ppMemBuffers, int size, int nNumBuffers)

Specify user allocated buffers to use as image data buffers.

 FLYCAPTURE2\_C\_API fc2Error fc2GetConfiguration (fc2Context context, fc2-Config \*config)

Get the configuration associated with the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetConfiguration (fc2Context context, fc2-Config \*config)

Set the configuration associated with the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCameraInfo (fc2Context context, fc2-CameraInfo \*pCameraInfo)

Retrieves information from the camera such as serial number, model name and other camera information.

 FLYCAPTURE2\_C\_API fc2Error fc2GetPropertyInfo (fc2Context context, fc2-PropertyInfo \*propInfo)

Retrieves information about the specified camera property.

 FLYCAPTURE2\_C\_API fc2Error fc2GetProperty (fc2Context context, fc2-Property \*prop)

Reads the settings for the specified property from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetProperty (fc2Context context, fc2-Property \*prop)

Writes the settings for the specified property to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetPropertyBroadcast (fc2Context context, fc2Property \*prop)

Writes the settings for the specified property to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int \*pDirection)

Get the GPIO pin direction for the specified pin.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGPIOPinDirectionBroadcast (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerModeInfo (fc2Context context, fc2TriggerModeInfo \*triggerModeInfo)

Retrieve trigger information from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerMode (fc2Context context, fc2-TriggerMode \*triggerMode)

Retrieve current trigger settings from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerMode (fc2Context context, fc2-TriggerMode \*triggerMode)

Set the specified trigger settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerModeBroadcast (fc2Context context, fc2TriggerMode \*triggerMode)

Set the specified trigger settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2FireSoftwareTrigger (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2\_C\_API fc2Error fc2FireSoftwareTriggerBroadcast (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerDelayInfo (fc2Context context, fc2TriggerDelayInfo \*triggerDelayInfo)

Retrieve trigger delay information from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetTriggerDelay (fc2Context context, fc2-TriggerDelay \*triggerDelay)

Retrieve current trigger delay settings from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerDelay (fc2Context context, fc2-TriggerDelay \*triggerDelay)

Set the specified trigger delay settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetTriggerDelayBroadcast (fc2Context context, fc2TriggerDelay \*triggerDelay)

Set the specified trigger delay settings to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetStrobeInfo (fc2Context context, fc2-StrobeInfo \*strobeInfo)

Retrieve strobe information from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetStrobe (fc2Context context, fc2Strobe-Control \*strobeControl)

Retrieve current strobe settings from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetStrobe (fc2Context context, fc2Strobe-Control \*strobeControl)

Set current strobe settings to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetStrobeBroadcast (fc2Context context, fc2StrobeControl \*strobeControl)

Set current strobe settings to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetLUTInfo (fc2Context context, fc2LUT-Data \*pData)

Query if LUT support is available on the camera.

• FLYCAPTURE2\_C\_API fc2Error fc2GetLUTBankInfo (fc2Context context, unsigned int bank, BOOL \*pReadSupported, BOOL \*pWriteSupported)

Query the read/write status of a single LUT bank.

FLYCAPTURE2\_C\_API fc2Error fc2GetActiveLUTBank (fc2Context context, unsigned int \*pActiveBank)

Get the LUT bank that is currently being used.

FLYCAPTURE2\_C\_API fc2Error fc2SetActiveLUTBank (fc2Context context, unsigned int activeBank)

Set the LUT bank that will be used.

• FLYCAPTURE2\_C\_API fc2Error fc2EnableLUT (fc2Context context, BOOL on)

Enable or disable LUT functionality on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int \*p-Entries)

Get the LUT channel settings from the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int \*p-Entries)

Set the LUT channel settings to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetMemoryChannel (fc2Context context, unsigned int \*pCurrentChannel)

Retrieve the current memory channel from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SaveToMemoryChannel (fc2Context context, unsigned int channel)

Save the current settings to the specified current memory channel.

 FLYCAPTURE2\_C\_API fc2Error fc2RestoreFromMemoryChannel (fc2Context context, unsigned int channel)

Restore the specified current memory channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetMemoryChannelInfo (fc2Context context, unsigned int \*pNumChannels)

Query the camera for memory channel support.

FLYCAPTURE2\_C\_API fc2Error fc2GetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo \*pInfo)

Get the current status of the embedded image information register, as well as the availability of each embedded property.

FLYCAPTURE2\_C\_API fc2Error fc2SetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo \*pInfo)

Sets the on/off values of the embedded image information structure to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegister (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2ReadRegister (fc2Context context, unsigned int address, unsigned int \*pValue)

Read the specified register from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2WriteRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera with broadcast.

FLYCAPTURE2\_C\_API fc2Error fc2WriteRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int \*pBuffer, unsigned int length)

Write to the specified register block on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2ReadRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int \*pBuffer, unsigned int length)

Write to the specified register block on the camera.

 FLYCAPTURE2\_C\_API const char \* fc2GetRegisterString (unsigned int register-Val)

Returns a text representation of the register value.

 FLYCAPTURE2\_C\_API fc2Error fc2GetCycleTime (fc2Context context, fc2Time-Stamp \*pTimeStamp)

Get cycle time from camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetStats (fc2Context context, fc2Camera-Stats \*pCameraStats) Returns the camera diagnostic information.

- FLYCAPTURE2 C API fc2Error ResetStats ()
- FLYCAPTURE2\_C\_API fc2Error fc2RegisterEvent (fc2Context context, fc2-EventOptions \*pOpts)

Register the camera to issue a custom callback function call for a specific device event.

 FLYCAPTURE2\_C\_API fc2Error fc2DeregisterEvent (fc2Context context, fc2-EventOptions \*pOpts)

De-register an event previously registered with the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2RegisterAllEvents (fc2Context context, fc2-EventOptions \*pOpts)

Register the camera to issue a custom callback function call for a specific device event.

- FLYCAPTURE2 C API fc2Error fc2DeregisterAllEvents (fc2Context context)
- FLYCAPTURE2\_C\_API fc2Error fc2GetVideoModeAndFrameRateInfo (fc2-Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL \*pSupported)

Query the camera to determine if the specified video mode and frame rate is supported.

FLYCAPTURE2\_C\_API fc2Error fc2GetVideoModeAndFrameRate (fc2Context context, fc2VideoMode \*videoMode, fc2FrameRate \*frameRate)

Get the current video mode and frame rate from the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetVideoModeAndFrameRate (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetFormat7Info (fc2Context context, fc2-Format7Info \*info, BOOL \*pSupported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

FLYCAPTURE2\_C\_API fc2Error fc2ValidateFormat7Settings (fc2Context context, fc2Format7ImageSettings \*imageSettings, BOOL \*settingsAreValid, fc2-Format7PacketInfo \*packetInfo)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

FLYCAPTURE2\_C\_API fc2Error fc2GetFormat7Configuration (fc2Context context, fc2Format7ImageSettings \*imageSettings, unsigned int \*packetSize, float \*percentage)

Get the current Format7 configuration from the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetFormat7ConfigurationPacket (fc2Context context, fc2Format7ImageSettings \*imageSettings, unsigned int packetSize)

Set the current Format7 configuration to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetFormat7Configuration (fc2Context context, fc2Format7ImageSettings \*imageSettings, float percentSpeed)

Set the current Format7 configuration to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegister (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register.

 FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register with broadcast.

FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPRegister (fc2Context context, unsigned int address, unsigned int \*pValue)

Read a GVCP register.

FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPRegisterBlock (fc2Context context, unsigned int address, const unsigned int \*pBuffer, unsigned int length)

Write a GVCP register block.

FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPRegisterBlock (fc2Context context, unsigned int address, unsigned int \*pBuffer, unsigned int length)

Read a GVCP register block.

FLYCAPTURE2\_C\_API fc2Error fc2WriteGVCPMemory (fc2Context context, unsigned int address, const unsigned char \*pBuffer, unsigned int length)

Write a GVCP memory block.

• FLYCAPTURE2\_C\_API fc2Error fc2ReadGVCPMemory (fc2Context context, unsigned int address, unsigned char \*pBuffer, unsigned int length)

Read a GVCP memory block.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEProperty (fc2Context context, fc2-GigEProperty \*pGigEProp)

Get the specified GigEProperty.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEProperty (fc2Context context, const fc2GigEProperty \*pGigEProp)

Set the specified GigEProperty.

FLYCAPTURE2\_C\_API fc2Error fc2DiscoverGigEPacketSize (fc2Context context, unsigned int \*packetSize)

Discover the largest packet size that works for the network link between the PC and the camera.

FLYCAPTURE2\_C\_API fc2Error fc2QueryGigElmagingMode (fc2Context context, fc2Mode mode, BOOL \*isSupported)

Check if the particular imaging mode is supported by the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImagingMode (fc2Context context, fc2Mode \*mode)

Get the current imaging mode on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImagingMode (fc2Context context, fc2Mode mode)

Set the current imaging mode to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageSettingsInfo (fc2Context context, fc2GigEImageSettingsInfo \*pInfo)

Get information about the image settings possible on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageSettings (fc2Context context, fc2GigEImageSettings \*pImageSettings)

Get the current image settings on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImageSettings (fc2Context context, const fc2GigEImageSettings \*pImageSettings)

Set the image settings specified to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageBinningSettings (fc2Context context, unsigned int \*horzBinnningValue, unsigned int \*vertBinnningValue)

Get the current binning settings on the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEImageBinningSettings (fc2Context context, unsigned int horzBinnningValue, unsigned int vertBinnningValue)

Set the specified binning values to the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetNumStreamChannels (fc2Context context, unsigned int \*numChannels)

Get the number of stream channels present on the camera.

FLYCAPTURE2\_C\_API fc2Error fc2GetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel \*pChannel)

Get the stream channel information for the specified channel.

FLYCAPTURE2\_C\_API fc2Error fc2SetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel \*pChannel)

Set the stream channel information for the specified channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetGigEConfig (fc2Context context, fc2Gig-EConfig \*pConfig)

Get the current gige config on the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetGigEConfig (fc2Context context, const fc2GigEConfig \*pConfig)

Set the gige config specified to the camera.

 FLYCAPTURE2\_C\_API fc2Error fc2SetDefaultColorProcessing (fc2Color-ProcessingAlgorithm defaultMethod)

Set the default color processing algorithm.

 FLYCAPTURE2\_C\_API fc2Error fc2GetDefaultColorProcessing (fc2Color-ProcessingAlgorithm \*pDefaultMethod)

Get the default color processing algorithm.

FLYCAPTURE2\_C\_API fc2Error fc2SetDefaultOutputFormat (fc2PixelFormat format)

Set the default output pixel format.

FLYCAPTURE2\_C\_API fc2Error fc2GetDefaultOutputFormat (fc2PixelFormat \*pFormat)

Get the default output pixel format.

FLYCAPTURE2\_C\_API fc2Error fc2DetermineBitsPerPixel (fc2PixelFormat format, unsigned int \*pBitsPerPixel)

Calculate the bits per pixel for the specified pixel format.

• FLYCAPTURE2\_C\_API fc2Error fc2CreateImage (fc2Image \*pImage)

Create a fc2lmage.

• FLYCAPTURE2\_C\_API fc2Error fc2DestroyImage (fc2Image \*image)

Destroy the fc2Image.

 FLYCAPTURE2\_C\_API fc2Error fc2SetImageDimensions (fc2Image \*pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixel-Format, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageDimensions (fc2Image \*pImage, unsigned int \*pRows, unsigned int \*pCols, unsigned int \*pStride, fc2PixelFormat \*pPixelFormat, fc2BayerTileFormat \*pBayerFormat)

Get the image dimensions associated with the image object.

• FLYCAPTURE2\_C\_API fc2Error fc2SetImageColorProcessing (fc2Image \*p-Image, fc2ColorProcessingAlgorithm colorProc)

Set the color processing algorithm.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageColorProcessing (fc2Image \*p-Image, fc2ColorProcessingAlgorithm \*pColorProc)

Get the current color processing algorithm.

• FLYCAPTURE2\_C\_API fc2Error fc2SetImageData (fc2Image \*pImage, const unsigned char \*pData, unsigned int dataSize)

Set the data of the Image object.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageData (fc2Image \*pImage, unsigned char \*\*ppData)

Get a pointer to the data associated with the image.

FLYCAPTURE2\_C\_API fc2Error fc2GetImageMetadata (fc2Image \*pImage, fc2-ImageMetadata \*pImageMetaData)

Get the metadata associated with the image.

FLYCAPTURE2\_C\_API fc2TimeStamp fc2GetImageTimeStamp (fc2Image \*p-Image)

Get the timestamp data associated with the image.

 FLYCAPTURE2\_C\_API fc2Error fc2SaveImage (fc2Image \*pImage, const char \*pFilename, fc2ImageFileFormat format)

Save the image to the specified file name with the file format specified.

 FLYCAPTURE2\_C\_API fc2Error fc2SaveImageWithOption (fc2Image \*pImage, const char \*pFilename, fc2ImageFileFormat format, void \*pOption)

Save the image to the specified file name with the file format specified.

- FLYCAPTURE2\_C\_API fc2Error fc2ConvertImage (fc2Image \*pImageIn, fc2-Image \*pImageOut)
- FLYCAPTURE2\_C\_API fc2Error fc2ConvertImageTo (fc2PixelFormat format, fc2Image \*pImageIn, fc2Image \*pImageOut)

Converts the current image buffer to the specified output format and stores the result in the specified image.

FLYCAPTURE2\_C\_API fc2Error fc2CalculateImageStatistics (fc2Image \*p-Image, fc2ImageStatisticsContext \*pImageStatisticsContext)

Calculate statistics associated with the image.

 FLYCAPTURE2\_C\_API fc2Error fc2CreateImageStatistics (fc2ImageStatistics-Context \*pImageStatisticsContext)

Create a statistics context.

 FLYCAPTURE2\_C\_API fc2Error fc2DestroyImageStatistics (fc2ImageStatistics-Context imageStatisticsContext)

Destroy a statistics context.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableAll (fc2Image-StatisticsContext imageStatisticsContext) Enable all channels.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsDisableAll (fc2Image-StatisticsContext imageStatisticsContext)

Disable all channels.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableGreyOnly (fc2Image-StatisticsContext imageStatisticsContext)

Enable only the grey channel.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableRGBOnly (fc2Image-StatisticsContext imageStatisticsContext)

Enable only the RGB channels.

 FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableHSLOnly (fc2Image-StatisticsContext imageStatisticsContext)

Enable only the HSL channels.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelStatus (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, BOOL \*p-Enabled)

Get the status of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2SetChannelStatus (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled)

Set the status of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelRange (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*pMin, unsigned int \*pMax)

Get the range of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelPixelValueRange (fc2Image-StatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*pPixelValueMin, unsigned int \*pPixelValueMax)

Get the range of a statistics channel.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelNumPixelValues (fc2Image-StatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*pNumPixelValues)

Get the number of unique pixel values in the image.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelMean (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, float \*pPixel-ValueMean)

Get the mean of the image.

 FLYCAPTURE2\_C\_API fc2Error fc2GetChannelHistogram (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, int \*\*pp-Histogram)

Get the histogram for the image.

 FLYCAPTURE2\_C\_API fc2Error fc2GetImageStatistics (fc2ImageStatistics-Context imageStatisticsContext, fc2StatisticsChannel channel, unsigned int \*p-RangeMin, unsigned int \*pRangeMax, unsigned int \*pPixelValueMin, unsigned int \*pPixelValueMax, unsigned int \*pNumPixelValues, float \*pPixelValueMean, int \*\*ppHistogram)

Get all statistics for the image.

FLYCAPTURE2\_C\_API fc2Error fc2CreateTopologyNode (fc2TopologyNodeContext \*pTopologyNodeContext)

Create a TopologyNode context.

 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetGuid (fc2TopologyNode-Context TopologyNodeContext, fc2PGRGuid \*pGuid)

Get the PGRGuid associated with the node.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetDeviceId (fc2Topology-NodeContext TopologyNodeContext, int \*pID)

Get the device ID associated with the node.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNodeType (fc2Topology-NodeContext TopologyNodeContext, fc2NodeType \*pNodeType)

Get the node type associated with the node.

 FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetInterfaceType (fc2-TopologyNodeContext TopologyNodeContext, fc2InterfaceType \*pInterface-Type)

Get the interface type associated with the node.

- FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumChildren (fc2-TopologyNodeContext TopologyNodeContext, unsigned int \*pNumChildNodes)
   Get the number of child nodes.
- FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetChild (fc2TopologyNodeContext TopologyNodeContext, unsigned int position, fc2TopologyNodeContext \*pChildTopologyNodeContext)

Get child node located at the specified position.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeAddChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeChild-Context)

Add the specified TopologyNode as a child of the node.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumPorts (fc2Topology-NodeContext TopologyNodeContext, unsigned int \*pNumPorts)

Get the number of ports.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetPortType (fc2Topology-NodeContext TopologyNodeContext, unsigned int position, fc2PortType \*pPortType)

Get type of port located at the specified position.

FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeAddPortType (fc2Topology-NodeContext TopologyNodeContext, fc2PortType portType)

Add the specified PortType as a port of the node.

- FLYCAPTURE2\_C\_API BOOL fc2TopologyNodeAssignGuidToNode (fc2-TopologyNodeContext TopologyNodeContext, fc2PGRGuid guid, int deviceId)
  - Assign a PGRGuid and device ID to the node.
- FLYCAPTURE2\_C\_API BOOL fc2TopologyNodeAssignGuidToNodeEx (fc2-TopologyNodeContext TopologyNodeContext, fc2PGRGuid guid, int deviceId, fc2NodeType nodeType)

Assign a PGRGuid, device ID and nodeType to the node.

 FLYCAPTURE2\_C\_API fc2Error fc2DestroyTopologyNode (fc2TopologyNode-Context TopologyNodeContext) Destroy a TopologyNode context.

FLYCAPTURE2\_C\_API fc2Error fc2CheckDriver (const fc2PGRGuid \*pGuid)
 Check for driver compatibility for the given camera guid.

• FLYCAPTURE2\_C\_API fc2Error fc2GetDriverDeviceName (const fc2PGRGuid \*pGuid, char \*pDeviceName, size t \*deviceNameLength)

Get the driver's name for a device.

FLYCAPTURE2\_C\_API fc2Error fc2GetSystemInfo (fc2SystemInfo \*pSystemInfo)

Get system information.

- FLYCAPTURE2\_C\_API fc2Error fc2GetLibraryVersion (fc2Version \*pVersion)
   Get library version.
- FLYCAPTURE2\_C\_API fc2Error fc2LaunchBrowser (const char \*pAddress)

  Launch a URL in the system default browser.
- FLYCAPTURE2\_C\_API fc2Error fc2LaunchHelp (const char \*pFileName)

  Open a CHM file in the system default CHM viewer.
- FLYCAPTURE2\_C\_API fc2Error fc2LaunchCommand (const char \*p-Command)

Execute a command in the terminal.

 FLYCAPTURE2\_C\_API fc2Error fc2LaunchCommandAsync (const char \*p-Command, fc2AsyncCommandCallback pCallback, void \*pUserData)

Execute a command in the terminal.

• FLYCAPTURE2\_C\_API const char \* fc2ErrorToDescription (fc2Error error)

Get a string representation of an error.

#### 8.1.1 Function Documentation

8.1.1.1 FLYCAPTURE2\_C\_API fc2Error fc2CreateContext ( fc2Context \* pContext )

Create a FC2 context for IIDC camera.

This call must be made before any other calls that use a context will succeed.

See also

fc2DestroyContext()

## **Parameters**

*pContext* A pointer to the fc2Context to be created.

#### Returns

A fc2Error indicating the success or failure of the function.

8.1.1.2 FLYCAPTURE2\_C\_API fc2Error fc2CreateGigEContext ( fc2Context \* pContext )

Create a FC2 context for a GigE Vision camera.

This call must be made before any other calls that use a context will succeed.

#### See also

fc2DestroyContext()

#### **Parameters**

pContext A pointer to the fc2Context to be created.
---

#### Returns

A fc2Error indicating the success or failure of the function.

- 8.1.1.3 FLYCAPTURE2\_C\_API fc2Error fc2DeregisterAllEvents (fc2Context context)
- 8.1.1.4 FLYCAPTURE2\_C\_API fc2Error fc2DeregisterEvent ( fc2Context context, fc2EventOptions \* pOpts )

De-register an event previously registered with the camera.

## Parameters

context	The fc2Context to be used.	
pOpts	Pointer to the EventOptions structure which defines the callback func-	
	tion to use, the event for which to register the device, and a pointer to	
	user data (optional) to be passed to the callback function. The callback	
	function and user data elements of the EventOptions structure are ig-	
	nored in this call, and just the event name within the structure is used	
	with this function call.	

#### Returns

An Error indicating the success or failure of the function.

8.1.1.5 FLYCAPTURE2\_C\_API fc2Error fc2DestroyContext ( fc2Context context )

Destroy the FC2 context.

This must be called when the user is finished with the context in order to prevent memory leaks.

#### See also

fc2CreateContext()

#### **Parameters**

context	The context to be destroyed.

#### **Returns**

A fc2Error indicating the success or failure of the function.

# 8.1.1.6 FLYCAPTURE2\_C\_API fc2Error fc2GetCycleTime ( fc2Context context, fc2TimeStamp \* pTimeStamp )

Get cycle time from camera.

#### **Parameters**

contex	The fc2Context to be used.
Timestam	struct.

#### Returns

A fc2Error indicating the success or failure of the function.

## 8.1.1.7 FLYCAPTURE2\_C\_API fc2Error fc2GetStats ( fc2Context context, fc2CameraStats \* pCameraStats )

Returns the camera diagnostic information.

#### **Parameters**

context	The fc2Context to be used.
pCamera-	Pointer to the fc2CameraStats structure.
Stats	

#### **Returns**

A fc2Error indicating the success or failure of the function.

# 8.1.1.8 FLYCAPTURE2\_C\_API fc2Error fc2RegisterAllEvents ( fc2Context context, fc2EventOptions \* pOpts )

Register the camera to issue a custom callback function call for a specific device event.

#### **Parameters**

context	The fc2Context to be used.	
pOpts	Pointer to the EventOptions structure which defines the callback func-	
	tion to use, the event for which to register the device, and a pointer	
	user data (optional) to be passed to the callback function. The eve	
	name element of the structure is ignored with this function call. If	
	single event has already been registered via RegisterEvent(), this call	
	will fail, as the user could accidentally change the the internal callback	
	function pointer for a queued event. The user will need to de-register all	
	registered events, then call this function again.	

#### Returns

An Error indicating the success or failure of the function.

## 8.1.1.9 FLYCAPTURE2\_C\_API fc2Error fc2RegisterEvent ( fc2Context context, fc2EventOptions \* pOpts )

Register the camera to issue a custom callback function call for a specific device event.

#### **Parameters**

context	The fc2Context to be used.	
pOpts	Pointer to the EventOptions structure which defines the callback func-	
tion to use, the event for which to register the device, and a pointer user data (optional) to be passed to the callback function.		

#### Returns

An Error indicating the success or failure of the function.

#### 8.1.1.10 FLYCAPTURE2\_C\_API fc2Error ResetStats ( )

## 8.2 FlyCapture2Defs\_C.h File Reference

## **Data Structures**

struct fc2PGRGuid

A GUID to the camera.

- struct fc2Image
- struct fc2SystemInfo

Description of the system.

struct fc2Version

The current version of the library.

struct fc2IPAddress

IPv4 address.

struct fc2MACAddress

MAC address.

struct fc2GigEProperty

A GigE property.

• struct fc2GigEStreamChannel

Information about a single GigE stream channel.

• struct fc2GigEConfig

Configuration for a GigE camera.

• struct fc2GigEImageSettingsInfo

Format 7 information for a single mode.

• struct fc2GigEImageSettings

Image settings for a GigE camera.

• struct fc2Format7ImageSettings

Format 7 image settings.

struct fc2Format7Info

Format 7 information for a single mode.

• struct fc2Format7PacketInfo

Format 7 packet information.

· struct fc2Config

Configuration for a camera.

• struct fc2TriggerDelayInfo

Information about a specific camera property.

struct fc2TriggerDelay

A specific camera property.

• struct fc2TriggerModeInfo

Information about a camera trigger property.

• struct fc2TriggerMode

A camera trigger.

struct fc2StrobeInfo

A camera strobe property.

• struct fc2StrobeControl

A camera strobe.

struct fc2TimeStamp

Timestamp information.

struct fc2ConfigROM

Camera configuration ROM.

· struct fc2CameraInfo

Camera information.

• struct fc2EmbeddedImageInfoProperty

Properties of a single embedded image info property.

· struct fc2EmbeddedImageInfo

212 File Documentation

Properties of the possible embedded image information.

• struct fc2ImageMetadata

Metadata related to an image.

struct fc2LUTData

Information about the camera's look up table.

struct fc2CameraStats

Camera diagnostic information.

· struct fc2PNGOption

Options for saving PNG images.

• struct fc2PPMOption

Options for saving PPM images.

• struct fc2PGMOption

Options for saving PGM images.

• struct fc2TIFFOption

Options for saving TIFF images.

• struct fc2JPEGOption

Options for saving JPEG image.

• struct fc2JPG2Option

Options for saving JPEG2000 image.

struct fc2BMPOption

Options for saving Bitmap image.

struct fc2EventOptions

Options for enabling device event registration.

• struct fc2EventCallbackData

#### **Defines**

- #define FALSE 0
- #define TRUE 1
- #define FULL\_32BIT\_VALUE 0x7FFFFFF
- #define MAX STRING LENGTH 512

## **Typedefs**

- · typedef int BOOL
- typedef void \* fc2Context

A context to the FlyCapture2 C library.

typedef void \* fc2GuiContext

A context to the FlyCapture2 C GUI library.

typedef void \* fc2lmagelmpl

An internal pointer used in the fc2lmage structure.

typedef void \* fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

- typedef void \* fc2TopologyNodeContext
  - A context referring to the TopologyNode object.
- typedef void \* fc2CallbackHandle
- typedef void(\* fc2BusEventCallback )(void \*pParameter, unsigned int serial-Number)
- typedef void(\* fc2ImageEventCallback)(fc2Image \*image, void \*pCallbackData)
- typedef void(\* fc2AsyncCommandCallback )(fc2Error retError, void \*pUserData)
- typedef void(\* fc2CameraEventCallback )(void \*pCallbackData)

#### **Enumerations**

• enum fc2Error { FC2 ERROR UNDEFINED = -1, FC2 ERROR OK, FC2-ERROR FAILED, FC2 ERROR NOT IMPLEMENTED, FC2 ERROR FAIL-ED BUS MASTER CONNECTION, FC2 ERROR NOT CONNECTED, FC2-ERROR\_INIT\_FAILED, FC2\_ERROR\_NOT\_INTITIALIZED, FC2\_ERROR\_I-NVALID\_PARAMETER, FC2\_ERROR\_INVALID\_SETTINGS, FC2\_ERROR\_-INVALID\_BUS\_MANAGER, FC2\_ERROR\_MEMORY\_ALLOCATION\_FAILED, FC2\_ERROR\_LOW\_LEVEL\_FAILURE, FC2\_ERROR\_NOT\_FOUND, FC2\_-ERROR\_FAILED\_GUID, FC2\_ERROR\_INVALID\_PACKET\_SIZE, FC2\_ERR-OR\_INVALID\_MODE, FC2\_ERROR\_NOT\_IN\_FORMAT7, FC2\_ERROR\_NO-T SUPPORTED, FC2 ERROR TIMEOUT, FC2 ERROR BUS MASTER F-AILED, FC2 ERROR INVALID GENERATION, FC2 ERROR LUT FAILED, FC2 ERROR IIDC FAILED, FC2 ERROR STROBE FAILED, FC2 ERRO-R TRIGGER FAILED, FC2 ERROR PROPERTY FAILED, FC2 ERROR P-ROPERTY NOT PRESENT, FC2 ERROR REGISTER FAILED, FC2 ERR-OR READ REGISTER FAILED, FC2 ERROR WRITE REGISTER FAILED, FC2\_ERROR\_ISOCH\_FAILED, FC2\_ERROR\_ISOCH\_ALREADY\_STARTED, FC2 ERROR ISOCH NOT STARTED, FC2 ERROR ISOCH START FAIL-ED, FC2\_ERROR\_ISOCH\_RETRIEVE\_BUFFER\_FAILED, FC2\_ERROR\_ISO-CH\_STOP\_FAILED, FC2\_ERROR\_ISOCH\_SYNC\_FAILED, FC2\_ERROR\_IS-OCH\_BANDWIDTH\_EXCEEDED, FC2\_ERROR\_IMAGE\_CONVERSION\_FAI-LED, FC2 ERROR IMAGE LIBRARY FAILURE, FC2 ERROR BUFFER T-OO SMALL, FC2 ERROR IMAGE CONSISTENCY ERROR, FC2 ERROR-\_INCOMPATIBLE\_DRIVER, FC2\_ERROR\_FORCE\_32BITS = FULL\_32BIT\_V-ALUE }

The error types returned by functions.

 enum fc2BusCallbackType { FC2\_BUS\_RESET, FC2\_ARRIVAL, FC2\_REMO-VAL, FC2\_CALLBACK\_TYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

The type of bus callback to register a callback function for.

enum fc2GrabMode { FC2\_DROP\_FRAMES, FC2\_BUFFER\_FRAMES, FC2\_UNSPECIFIED\_GRAB\_MODE, FC2\_GRAB\_MODE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

The grab strategy employed during image transfer.

enum fc2GrabTimeout { FC2\_TIMEOUT\_NONE = 0, FC2\_TIMEOUT\_INFINITE = -1, FC2\_TIMEOUT\_UNSPECIFIED = -2, FC2\_GRAB\_TIMEOUT\_FORCE\_-32BITS = FULL\_32BIT\_VALUE }

Timeout options for grabbing images.

enum fc2BandwidthAllocation { FC2\_BANDWIDTH\_ALLOCATION\_OFF = 0, FC2\_BANDWIDTH\_ALLOCATION\_ON = 1, FC2\_BANDWIDTH\_ALLOCATION\_UNSUPPORTED = 2, FC2\_BANDWIDTH\_ALLOCATION\_UNSPECIFIED = 3, FC2\_BANDWIDTH\_ALLOCATION\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Bandwidth allocation options for 1394 devices.

enum fc2InterfaceType { FC2\_INTERFACE\_IEEE1394, FC2\_INTERFACE\_USB\_2, FC2\_INTERFACE\_USB\_3, FC2\_INTERFACE\_GIGE, FC2\_INTERFACE\_UNKNOWN, FC2\_INTERFACE\_TYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Interfaces that a camera may use to communicate with a host.

enum fc2PropertyType { FC2\_BRIGHTNESS, FC2\_AUTO\_EXPOSURE, FC2\_SHARPNESS, FC2\_WHITE\_BALANCE, FC2\_HUE, FC2\_SATURATION, F-C2\_GAMMA, FC2\_IRIS, FC2\_FOCUS, FC2\_ZOOM, FC2\_PAN, FC2\_TILT, FC2\_SHUTTER, FC2\_GAIN, FC2\_TRIGGER\_MODE, FC2\_TRIGGER\_DELA-Y, FC2\_FRAME\_RATE, FC2\_TEMPERATURE, FC2\_UNSPECIFIED\_PROPERTY\_TYPE, FC2\_PROPERTY\_TYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE
 }

#### Camera properties.

enum fc2FrameRate { FC2\_FRAMERATE\_1\_875, FC2\_FRAMERATE\_3\_75, FC2\_FRAMERATE\_7\_5, FC2\_FRAMERATE\_15, FC2\_FRAMERATE\_30, F-C2\_FRAMERATE\_60, FC2\_FRAMERATE\_120, FC2\_FRAMERATE\_240, F-C2\_FRAMERATE\_FORMAT7, FC2\_NUM\_FRAMERATES, FC2\_FRAMERATE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

#### Frame rates in frames per second.

enum fc2VideoMode { FC2\_VIDEOMODE\_160x120YUV444, FC2\_VIDEOMODE\_320x240YUV422, FC2\_VIDEOMODE\_640x480YUV411, FC2\_VIDEOMODE\_640x480YUV422, FC2\_VIDEOMODE\_640x480RGB, FC2\_VIDEOMODE\_640x480Y8, FC2\_VIDEOMODE\_640x480Y16, FC2\_VIDEOMODE\_800x600-YUV422, FC2\_VIDEOMODE\_800x600RGB, FC2\_VIDEOMODE\_800x600Y8, FC2\_VIDEOMODE\_800x600Y16, FC2\_VIDEOMODE\_1024x768YUV422, FC2\_VIDEOMODE\_1024x768RGB, FC2\_VIDEOMODE\_1024x768Y8, FC2\_VIDEOMODE\_1024x768Y16, FC2\_VIDEOMODE\_1280x960YUV422, FC2\_VIDEOMODE\_1280x960RGB, FC2\_VIDEOMODE\_1280x960Y8, FC2\_VIDEOMODE\_1280x960Y16, FC2\_VIDEOMODE\_1600x1200YUV422, FC2\_VIDEOMODE\_1600x1200RGB, FC2\_VIDEOMODE\_1600x1200YUV422, FC2\_VIDEOMODE\_1600x1200RGB, FC2\_VIDEOMODE\_1600x1200Y16, FC2\_VIDEOMODE\_1600x1200Y8, FC2\_VIDEOMODE\_1600x1200Y16, FC2\_VIDEOMODE\_FORMAT7, FC2\_NUM\_VIDEOMODES, FC2\_VIDEOMODE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

#### DCAM video modes.

enum fc2Mode { FC2\_MODE\_0 = 0, FC2\_MODE\_1, FC2\_MODE\_2, FC2\_MODE\_3, FC2\_MODE\_4, FC2\_MODE\_5, FC2\_MODE\_6, FC2\_MODE\_7, FC2\_MODE\_8, FC2\_MODE\_9, FC2\_MODE\_10, FC2\_MODE\_11, FC2\_MODE\_12, FC2\_MODE\_13, FC2\_MODE\_14, FC2\_MODE\_15, FC2\_MODE\_16, FC2\_MODE\_17, FC2\_MODE\_18, FC2\_MODE\_19, FC2\_MODE\_20, FC2\_MODE\_21, FC2\_MODE\_22, FC2\_MODE\_23, FC2\_MODE\_24, FC2\_MODE\_25, FC2\_MODE\_26, FC2\_MODE\_27, FC2\_MODE\_28, FC2\_MODE\_29, FC2\_MODE\_30, FC2\_MODE\_31, FC2\_NUM\_MODES, FC2\_MODE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Camera modes for DCAM formats as well as Format7.

enum fc2PixelFormat { FC2\_PIXEL\_FORMAT\_MONO8 = 0x80000000, F-C2\_PIXEL\_FORMAT\_411YUV8 = 0x40000000, FC2\_PIXEL\_FORMAT\_422-YUV8 = 0x20000000, FC2\_PIXEL\_FORMAT\_444YUV8 = 0x100000000, F-C2\_PIXEL\_FORMAT\_RGB8 = 0x080000000, FC2\_PIXEL\_FORMAT\_MONO16 = 0x04000000, FC2\_PIXEL\_FORMAT\_RGB16 = 0x020000000, FC2\_PIXEL\_FORMAT\_S\_MONO16 = 0x010000000, FC2\_PIXEL\_FORMAT\_S\_RGB16 = 0x008000000, FC2\_PIXEL\_FORMAT\_RAW8 = 0x004000000, FC2\_PIXEL\_FORMAT\_RAW16 = 0x002000000, FC2\_PIXEL\_FORMAT\_MONO12 = 0x001000000, FC2\_PIXEL\_FORMAT\_RAW12 = 0x000800000, FC2\_PIXEL\_FORMAT\_BGR = 0x800000008, FC2\_PIXEL\_FORMAT\_BGRU = 0x40000008, FC2\_PIXEL\_FORMAT\_RGBU = 0x400000002, FC2\_PIXEL\_FORMAT\_RGB8, FC2\_PIXEL\_FORMAT\_RGBU = 0x40000002, FC2\_PIXEL\_FORMAT\_BGR16 = 0x020000001, FC2\_PIXEL\_FORMAT\_BGR16 = 0x02000001, FC2\_PIXEL\_FORMAT\_B

Pixel formats available for Format7 modes.

enum fc2BusSpeed { FC2\_BUSSPEED\_S100, FC2\_BUSSPEED\_S200, FC2\_BUSSPEED\_S400, FC2\_BUSSPEED\_S480, FC2\_BUSSPEED\_S800, FC2\_BUSSPEED\_S1600, FC2\_BUSSPEED\_S3200, FC2\_BUSSPEED\_S5000, × FC2\_BUSSPEED\_10BASE\_T, FC2\_BUSSPEED\_1000BASE\_T, FC2\_BUSSPEED\_S2-ED\_1000BASE\_T, FC2\_BUSSPEED\_S2-FASTEST, FC2\_BUSSPEED\_ANY, FC2\_BUSSPEED\_SPEED\_UNKNOWN = -1, FC2\_BUSSPEED\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Bus speeds.

- enum fc2PCleBusSpeed { FC2\_PCIE\_BUSSPEED\_2\_5, FC2\_PCIE\_BUSSPEED\_5\_0, FC2\_PCIE\_BUSSPEED\_UNKNOWN = -1, FC2\_PCIE\_BUSSPEED\_-FORCE\_32BITS = FULL\_32BIT\_VALUE }
- enum fc2DriverType { FC2\_DRIVER\_1394\_CAM, FC2\_DRIVER\_1394\_PRO, FC2\_DRIVER\_1394\_JUJU, FC2\_DRIVER\_1394\_VIDEO1394, FC2\_DRIVER\_R\_1394\_RAW1394, FC2\_DRIVER\_USB\_NONE, FC2\_DRIVER\_USB\_CAM, FC2\_DRIVER\_USB3\_PRO, FC2\_DRIVER\_GIGE\_NONE, FC2\_DRIVER\_GIGE\_FILTER, FC2\_DRIVER\_GIGE\_PRO, FC2\_DRIVER\_GIGE\_LWF, FC2\_DRIVER\_UNKNOWN = -1, FC2\_DRIVER\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Types of low level drivers that FlyCapture uses.

enum fc2ColorProcessingAlgorithm { FC2\_DEFAULT, FC2\_NO\_COLOR\_PR-OCESSING, FC2\_NEAREST\_NEIGHBOR\_FAST, FC2\_EDGE\_SENSING, × FC2\_HQ\_LINEAR, FC2\_RIGOROUS, FC2\_IPP, FC2\_DIRECTIONAL, FC2\_WEIGHTED\_DIRECTIONAL, FC2\_COLOR\_PROCESSING\_ALGORITHM\_FO-RCE\_32BITS = FULL\_32BIT\_VALUE }

Color processing algorithms.

enum fc2BayerTileFormat { FC2\_BT\_NONE, FC2\_BT\_RGGB, FC2\_BT\_GRB-G, FC2\_BT\_GBRG, FC2\_BT\_BGGR, FC2\_BT\_FORCE\_32BITS = FULL\_32B-IT\_VALUE }

Bayer tile formats.

enum fc2ImageFileFormat { FC2\_FROM\_FILE\_EXT = -1, FC2\_PGM, FC2\_P-PM, FC2\_BMP, FC2\_JPEG, FC2\_JPEG2000, FC2\_TIFF, FC2\_PNG, FC2-PM, FC2\_PNG, FC2\_P

216 File Documentation

```
_RAW, FC2_IMAGE_FILE_FORMAT_FORCE_32BITS = FULL_32BIT_VALUE }
```

File formats to be used for saving images to disk.

 enum fc2GigEPropertyType { FC2\_HEARTBEAT, FC2\_HEARTBEAT\_TIMEO-UT, PACKET SIZE, PACKET DELAY }

Possible properties that can be queried from the camera.

enum fc2StatisticsChannel { FC2\_STATISTICS\_GREY, FC2\_STATISTICS\_R-ED, FC2\_STATISTICS\_GREEN, FC2\_STATISTICS\_BLUE, FC2\_STATISTICS\_HUE, FC2\_STATISTICS\_SATURATION, FC2\_STATISTICS\_LIGHTNESS, FC2\_STATISTICS\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Channels that allow statistics to be calculated.

enum fc2OSType { FC2\_WINDOWS\_X86, FC2\_WINDOWS\_X64, FC2\_LINU-X\_X86, FC2\_LINUX\_X64, FC2\_MAC, FC2\_UNKNOWN\_OS, FC2\_OSTYPE\_FORCE\_32BITS = FULL\_32BIT\_VALUE }

Possible operating systems.

enum fc2ByteOrder { FC2\_BYTE\_ORDER\_LITTLE\_ENDIAN, FC2\_BYTE\_ORDER\_BIG\_ENDIAN, FC2\_BYTE\_ORDER\_FORCE\_32BITS = FULL\_32BIT\_V-ALUE }

Possible byte orders.

 enum fc2PortType { NOT\_CONNECTED = 1, CONNECTED\_TO\_PARENT, CONNECTED\_TO\_CHILD }

Possible states of a port on a node.

- enum fc2NodeType { COMPUTER, BUS, CAMERA, NODE }
   Type of node.
- enum fc2TIFFCompressionMethod { FC2\_TIFF\_NONE = 1, FC2\_TIFF\_PACK-BITS, FC2\_TIFF\_DEFLATE, FC2\_TIFF\_ADOBE\_DEFLATE, FC2\_TIFF\_CCI-TTFAX3, FC2\_TIFF\_CCITTFAX4, FC2\_TIFF\_LZW, FC2\_TIFF\_JPEG }

## 8.2.1 Enumeration Type Documentation

8.2.1.1 enum fc2ByteOrder

Possible byte orders.

**Enumerator:** 

FC2\_BYTE\_ORDER\_LITTLE\_ENDIAN FC2\_BYTE\_ORDER\_BIG\_ENDIAN FC2\_BYTE\_ORDER\_FORCE\_32BITS

8.2.1.2 enum fc2NodeType

Type of node.

#### **Enumerator:**

COMPUTER

BUS

**CAMERA** 

NODE

#### 8.2.1.3 enum fc2OSType

Possible operating systems.

#### **Enumerator:**

FC2\_WINDOWS\_X86 All Windows 32-bit variants.

FC2\_WINDOWS\_X64 All Windows 64-bit variants.

FC2\_LINUX\_X86 All Linux 32-bit variants.

FC2\_LINUX\_X64 All Linux 32-bit variants.

FC2\_MAC Mac OSX.

FC2\_UNKNOWN\_OS Unknown operating system.

FC2\_OSTYPE\_FORCE\_32BITS

#### 8.2.1.4 enum fc2PortType

Possible states of a port on a node.

## **Enumerator:**

NOT\_CONNECTED
CONNECTED\_TO\_PARENT
CONNECTED\_TO\_CHILD

## 8.2.1.5 enum fc2StatisticsChannel

Channels that allow statistics to be calculated.

#### **Enumerator:**

FC2\_STATISTICS\_GREY

FC2\_STATISTICS\_RED

FC2\_STATISTICS\_GREEN

FC2\_STATISTICS\_BLUE

FC2\_STATISTICS\_HUE

FC2\_STATISTICS\_SATURATION

FC2\_STATISTICS\_LIGHTNESS

FC2\_STATISTICS\_FORCE\_32BITS

## 8.3 FlyCapture2GUI\_C.h File Reference

#### **Functions**

 FLYCAPTURE2\_C\_API fc2Error fc2CreateGUIContext (fc2GuiContext \*p-Context)

Create a GUI context.

FLYCAPTURE2\_C\_API fc2Error fc2DestroyGUIContext (fc2GuiContext context)

Destroy a GUI context.

FLYCAPTURE2\_C\_API void fc2GUIConnect (fc2GuiContext context, fc2Context cameraContext)

Connect GUI context to a camera context.

• FLYCAPTURE2 C API void fc2GUIDisconnect (fc2GuiContext context)

Disconnect GUI context from camera.

 FLYCAPTURE2\_C\_API void fc2Disonnect (fc2GuiContext context) \_\_attribute\_-\_((deprecated))

Disconnect GUI context from camera.

• FLYCAPTURE2\_C\_API void fc2Show (fc2GuiContext context)

Show the GUI.

FLYCAPTURE2\_C\_API void fc2Hide (fc2GuiContext context)

Hide the GUI.

FLYCAPTURE2\_C\_API BOOL fc2IsVisible (fc2GuiContext context)

Check if the GUI is visible.

 FLYCAPTURE2\_C\_API void fc2ShowModal (fc2GuiContext context, BOOL \*p-OkSelected, fc2PGRGuid \*guidArray, unsigned int \*size)

Show the camera selection dialog.

#### 8.3.1 Function Documentation

#### 8.3.1.1 FLYCAPTURE2\_C\_API fc2Error fc2CreateGUIContext ( fc2GuiContext \* pContext )

Create a GUI context.

Any GigE cameras that were connected prior to this call will lose CCP after the call. Consider creating a GUI context prior to connecting any GigE cameras or calling connect on any outstanding GigE camera context.

#### **Parameters**

pContext	Pointer to context to be created.
----------	-----------------------------------

#### Returns

An Error indicating the success or failure of the function.

#### 8.3.1.2 FLYCAPTURE2\_C\_API fc2Error fc2DestroyGUIContext ( fc2GuiContext context )

Destroy a GUI context.

#### **Parameters**

context   Context to be destroyed.	

#### **Returns**

An Error indicating the success or failure of the function.

## 8.3.1.3 FLYCAPTURE2\_C\_API void fc2Disonnect ( fc2GuiContext context )

Disconnect GUI context from camera.

#### **Parameters**

context	GUI context to disconnect.
---------	----------------------------

#### **Returns**

An Error indicating the success or failure of the function.

**Deprecated** This method is deprecated and will be removed in a future FlyCapture2 release. Please use fc2GUIDisconnect instead.

# 8.3.1.4 FLYCAPTURE2\_C\_API void fc2GUIConnect ( fc2GuiContext context, fc2Context cameraContext )

Connect GUI context to a camera context.

## **Parameters**

context	GUI context to connect.
camera-	Camera context to connect.
Context	

## Returns

An Error indicating the success or failure of the function.

#### 8.3.1.5 FLYCAPTURE2\_C\_API void fc2GUIDisconnect (fc2GuiContext context)

Disconnect GUI context from camera.

#### **Parameters**

context	GUI context to	disconnect.
---------	----------------	-------------

#### Returns

An Error indicating the success or failure of the function.

## 8.3.1.6 FLYCAPTURE2\_C\_API void fc2Hide ( fc2GuiContext context )

Hide the GUI.

#### **Parameters**

context Po	inter to context to hide.
------------	---------------------------

#### Returns

An Error indicating the success or failure of the function.

## 8.3.1.7 FLYCAPTURE2\_C\_API BOOL fc2lsVisible (fc2GuiContext context)

Check if the GUI is visible.

## **Parameters**

context	Pointer to context to show.

#### Returns

Whether the GUI is visible.

## 8.3.1.8 FLYCAPTURE2\_C\_API void fc2Show ( fc2GuiContext context )

Show the GUI.

#### **Parameters**

context	Pointer to context to show.

#### Returns

An Error indicating the success or failure of the function.

8.3.1.9 FLYCAPTURE2\_C\_API void fc2ShowModal ( fc2GuiContext context, BOOL \* pOkSelected, fc2PGRGuid \* guidArray, unsigned int \* size )

Show the camera selection dialog.

#### **Parameters**

context	Pointer to context to show.
pOkSelected	Whether Ok (true) or Cancel (false) was clicked.
guidArray	Array of PGRGuids containing the selected cameras.
size	Size of PGRGuid array.

## 8.4 FlyCapture2Internal\_C.h File Reference

#### **Data Structures**

- · struct fc2InternalContext
- struct fc2InternalGuiContext
- · struct fc2InternalImageCallback

#### **Functions**

- bool IsContextValid (fc2Context context)
- bool IsGuiContextValid (fc2GuiContext context)
- void SyncCppImageToStruct (fc2Image \*pImage)

#### 8.4.1 Function Documentation

- 8.4.1.1 bool lsContextValid (fc2Context context) [inline]
- **8.4.1.2 bool IsGuiContextValid (fc2GuiContext context )** [inline]
- **8.4.1.3** void SyncCppImageToStruct (fc2Image \* pImage ) [inline]

## 8.5 FlyCapture2Platform\_C.h File Reference

#### **Defines**

- #define FLYCAPTURE2 C API
- #define FLYCAPTURE2\_C\_CALL\_CONVEN

## 8.5.1 Define Documentation

- 8.5.1.1 #define FLYCAPTURE2\_C\_API
- 8.5.1.2 #define FLYCAPTURE2\_C\_CALL\_CONVEN

## 8.6 FlyCapture2Private\_C.h File Reference

#### **Functions**

- FLYCAPTURE2\_C\_API void \* GetInternal (unsigned int index)
- 8.6.1 Function Documentation
- 8.6.1.1 FLYCAPTURE2\_C\_API void\* GetInternal ( unsigned int index )

## 8.7 FlyCapture2Video\_C.h File Reference

#### **Functions**

FLYCAPTURE2\_C\_API fc2Error fc2VideoCreate (fc2VideoContext \*pVideo-Context)

Create a Video context.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoAVIOpen (fc2VideoContext Video-Context, const char \*pFileName, fc2AVIOption \*pOption)

Open an AVI file in preparation for writing Images to disk.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoMJPGOpen (fc2VideoContext Video-Context, const char \*pFileName, fc2MJPGOption \*pOption)

Open an MJPEG file in preparation for writing Images to disk.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoH264Open (fc2VideoContext Video-Context, const char \*pFileName, fc2H264Option \*pOption)

Open an H.264 video file in preparation for writing Images to disk.

FLYCAPTURE2\_C\_API fc2Error fc2VideoAppend (fc2VideoContext Video-Context, fc2Image \*pImage)

Append an image to the video file.

FLYCAPTURE2\_C\_API fc2Error fc2VideoSetMaximumSize (fc2VideoContext - VideoContext, unsigned int size)

Set the maximum file size (in megabytes) of a AVI/MP4 file.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoClose (fc2VideoContext Video-Context)

Close the video file.

 FLYCAPTURE2\_C\_API fc2Error fc2VideoDestroy (fc2VideoContext Video-Context)

Destroy a video context.

## 8.8 FlyCapture2VideoDefs\_C.h File Reference

#### **Data Structures**

struct fc2MJPGOption

Options for saving MJPG files.

• struct fc2H264Option

Options for saving H264 files.

• struct fc2AVIOption

Options for saving AVI files.

#### **Typedefs**

• typedef void \* fc2VideoContext

A context referring to the video recorder object.

## 8.9 Licensing.dox File Reference

## 8.10 MultiSyncLibrary\_C.h File Reference

#### **Functions**

 MULTISYNCLIBRARY\_C\_API syncError syncCreateContext (syncContext \*p-Context)

Create a Sync context for MultiSync Library.

MULTISYNCLIBRARY\_C\_API syncError syncDestroyContext (syncContext context)

Destory the sync context.

- MULTISYNCLIBRARY\_C\_API syncError syncStart (syncContext context)
   Start the sync progress.
- MULTISYNCLIBRARY\_C\_API syncError syncStop (syncContext context)
   Stop the sync progress.
- MULTISYNCLIBRARY\_C\_API syncError syncRescanMasterTimingBus (sync-Context context)

Scan newly connected or removed timing bus (for corss-PC syncing only)

MULTISYNCLIBRARY\_C\_API syncMessage syncGetStatus (syncContext context)

Start the sync progress.

 MULTISYNCLIBRARY\_C\_API double syncGetTimeSinceSynced (syncContext context)

Time since sync started.

 MULTISYNCLIBRARY\_C\_API BOOL synclsTimingBusConnected (syncContext context) Whether syncing across PCs.

 MULTISYNCLIBRARY\_C\_API BOOL syncEnableCrossPCSynchronization (syncContext context)

Enable across pc synchronization support.

 MULTISYNCLIBRARY\_C\_API BOOL syncDisableCrossPCSynchronization (syncContext context)

Disable across pc synchronization support.

 MULTISYNCLIBRARY\_C\_API BOOL syncQueryCrossPCSynchronization-Setting (syncContext context)

Query cross pc synchronizaion support status.

#### 8.10.1 Function Documentation

8.10.1.1 MULTISYNCLIBRARY\_C\_API syncError syncCreateContext ( syncContext \* pContext )

Create a Sync context for MultiSync Library.

This call must be made before any other calls that use a context will succeed.

#### **Parameters**

pContext	A pointe	to the syncConte	ext to be created.
----------	----------	------------------	--------------------

#### Returns

A syncError indicating the success or failure of the function.

8.10.1.2 MULTISYNCLIBRARY\_C\_API syncError syncDestroyContext ( syncContext context )

Destory the sync context.

This must be called when the user is finished with the context in order to prevent memory leaks.

#### **Parameters**

context The syncContext to be destoryed.

Returns

A syncError indicating the success or failure of the function.

8.10.1.3 MULTISYNCLIBRARY\_C\_API BOOL syncDisableCrossPCSynchronization ( syncContext context )

Disable across pc synchronization support.

#### **Parameters**

context   The syncContext to be used.
---------------------------------------

#### Returns

True if operation was successful

8.10.1.4 MULTISYNCLIBRARY\_C\_API BOOL syncEnableCrossPCSynchronization ( syncContext context )

Enable across pc synchronization support.

## Parameters

context	The syncContext to be used.

#### **Returns**

True if operation was successful

8.10.1.5 MULTISYNCLIBRARY\_C\_API syncMessage syncGetStatus ( syncContext context )

Start the sync progress.

#### **Parameters**

context The syncContext to be used.

Returns

A syncMessage indicating the sync status.

8.10.1.6 MULTISYNCLIBRARY\_C\_API double syncGetTimeSinceSynced ( syncContext context )

Time since sync started.

#### **Parameters**

context The s	syncContext to be used.

#### Returns

Time sinced synced.

8.10.1.7 MULTISYNCLIBRARY\_C\_API BOOL synclsTimingBusConnected ( syncContext context )

Whether syncing across PCs.

## **Parameters**

contex	The syncContext to be used.
--------	-----------------------------

#### Returns

True if its syncing across PC

8.10.1.8 MULTISYNCLIBRARY\_C\_API BOOL syncQueryCrossPCSynchronizationSetting ( syncContext context )

Query cross pc synchronizaion support status.

#### **Parameters**

context The syncContext to be used.
-------------------------------------

#### **Returns**

True if cross pc synchronization was supported

8.10.1.9 MULTISYNCLIBRARY\_C\_API syncError syncRescanMasterTimingBus ( syncContext context )

Scan newly connected or removed timing bus (for corss-PC syncing only)

#### **Parameters**

context	The syncContext to be used.

#### Returns

A syncError indicating the success or failure of the function.

8.10.1.10 MULTISYNCLIBRARY\_C\_API syncError syncStart ( syncContext context )

Start the sync progress.

## **Parameters**

context	The syncContext to be used.

# Returns

A syncError indicating the success or failure of the function.

8.10.1.11 MULTISYNCLIBRARY\_C\_API syncError syncStop ( syncContext context )

Stop the sync progress.

#### **Parameters**

context	The syncContext to be used.	

#### **Returns**

A syncError indicating the success or failure of the function.

# 8.11 MultiSyncLibraryDefs\_C.h File Reference

#### **Defines**

- #define FALSE 0
- #define TRUE 1
- #define FULL\_32BIT\_VALUE 0x7FFFFFF
- #define MAX\_STRING\_LENGTH 512

# **Typedefs**

- typedef int BOOL
- typedef void \* syncContext

A context to the MultiSync C library.

#### **Enumerations**

- enum syncError { SYNC\_ERROR\_OK = 0, SYNC\_ERROR\_FAILED, SYN-C\_ERROR\_ALREADY\_STARTED, SYNC\_ERROR\_ALREADY\_STOPPED, S-YNC\_ERROR\_CONTEXT\_NOT\_INITIALIZED, SYNC\_ERROR\_UNKNOWN\_E-RROR }
- enum syncMessage { SYNC\_MESSAGE\_OK = 0, SYNC\_MESSAGE\_FAILED, SYNC\_MESSAGE\_STARTED, SYNC\_MESSAGE\_STOPPED, SYNC\_MESS-AGE\_SYNCING, SYNC\_MESSAGE\_NOMASTER, SYNC\_MESSAGE\_THRE-AD\_ERROR, SYNC\_MESSAGE\_DEVICE\_ERROR, SYNC\_MESSAGE\_NOT\_ENOUGH\_DEVICES, SYNC\_MESSAGE\_BUS\_RESET, SYNC\_MESSAGE\_NOT\_INITIALIZED, SYNC\_MESSAGE\_UNKNOWN\_ERROR }
- 8.11.1 Define Documentation
- 8.11.1.1 #define FALSE 0
- 8.11.1.2 #define FULL\_32BIT\_VALUE 0x7FFFFFF
- 8.11.1.3 #define MAX\_STRING\_LENGTH 512
- 8.11.1.4 #define TRUE 1
- 8.11.2 Typedef Documentation
- 8.11.2.1 typedef int BOOL
- 8.11.2.2 typedef void\* syncContext

A context to the MultiSync C library.

It must be created before performing any calls to the library.

## 8.11.3 Enumeration Type Documentation

#### 8.11.3.1 enum syncError

#### **Enumerator:**

SYNC\_ERROR\_OK
SYNC\_ERROR\_FAILED
SYNC\_ERROR\_ALREADY\_STARTED
SYNC\_ERROR\_ALREADY\_STOPPED
SYNC\_ERROR\_CONTEXT\_NOT\_INITIALIZED
SYNC\_ERROR\_UNKNOWN\_ERROR

#### 8.11.3.2 enum syncMessage

#### **Enumerator:**

SYNC\_MESSAGE\_OK
SYNC\_MESSAGE\_FAILED
SYNC\_MESSAGE\_STARTED
SYNC\_MESSAGE\_STOPPED
SYNC\_MESSAGE\_SYNCING
SYNC\_MESSAGE\_NOMASTER
SYNC\_MESSAGE\_THREAD\_ERROR
SYNC\_MESSAGE\_DEVICE\_ERROR
SYNC\_MESSAGE\_NOT\_ENOUGH\_DEVICES
SYNC\_MESSAGE\_BUS\_RESET
SYNC\_MESSAGE\_NOT\_INITIALIZED
SYNC\_MESSAGE\_UNKNOWN\_ERROR

# 8.12 MultiSyncLibraryPlatform\_C.h File Reference

### **Defines**

- #define MULTISYNCLIBRARY\_C\_API
- #define MULTISYNCLIBRARY\_C\_CALL\_CONVEN

# 8.12.1 Define Documentation

- 8.12.1.1 #define MULTISYNCLIBRARY C API
- 8.12.1.2 #define MULTISYNCLIBRARY\_C\_CALL\_CONVEN

# Index

DUIO	F00 PH00PFFP 0400 444
BUS	FC2_BUSSPEED_S100, 111
FlyCapture2Defs_C.h, 217	FC2_BUSSPEED_S1600, 111
CAMERA	FC2_BUSSPEED_S200, 111
FlyCapture2Defs_C.h, 217	FC2_BUSSPEED_S3200, 111
COMPUTER	FC2_BUSSPEED_S400, 111
FlyCapture2Defs_C.h, 217	FC2_BUSSPEED_S480, 111
CONNECTED_TO_CHILD	FC2_BUSSPEED_S5000, 111
FlyCapture2Defs_C.h, 217	FC2_BUSSPEED_S800, 111
CONNECTED_TO_PARENT	FC2_BUSSPEED_SPEED_UNKNO-
FlyCapture2Defs_C.h, 217	WN, 111
Enumerations	FC2_BUSSPEED_S_FASTEST, 111
FC2_ARRIVAL, 110	FC2_BUS_RESET, 110
FC2_AUTO_EXPOSURE, 118	FC2_CALLBACK_TYPE_FORCE
FC2_BANDWIDTH_ALLOCATION	32BITS, 110
FORCE_32BITS, 110	FC2_COLOR_PROCESSING_AL-
FC2 BANDWIDTH ALLOCATION -	GORITHM_FORCE_32BITS,
OFF, 110	112
FC2_BANDWIDTH_ALLOCATION	FC2 DEFAULT, 111
ON, 110	FC2 DIRECTIONAL, 111
FC2 BANDWIDTH ALLOCATION -	FC2 DRIVER 1394 CAM, 112
UNSPECIFIED, 110	FC2 DRIVER 1394 JUJU, 112
FC2 BANDWIDTH ALLOCATION -	FC2_DRIVER_1394_PRO, 112
UNSUPPORTED, 110	FC2_DRIVER_1394_RAW1394, 112
FC2 BMP, 115	FC2_DRIVER_1394_VIDEO1394,
FC2 BRIGHTNESS, 118	112
FC2 BT BGGR, 110	FC2 DRIVER FORCE 32BITS, 112
FC2_BT_FORCE_32BITS, 110	FC2 DRIVER GIGE FILTER, 112
FC2_BT_GBRG, 110	FC2_DRIVER_GIGE_LWF, 112
FC2_BT_GRBG, 110	FC2_DRIVER_GIGE_NONE, 112
FC2 BT NONE, 110	FC2 DRIVER GIGE PRO, 112
FC2_BT_NGNE, TT0	FC2_DRIVER_UNKNOWN, 112
FC2 BUFFER FRAMES, 114	FC2 DRIVER USB3 PRO, 112
FC2_BUSSPEED_10000BASE_T,	FC2 DRIVER USB CAM, 112
102_B0331 EED_10000BA3E_1,	FC2_DRIVER_USB_NONE, 112
FC2_BUSSPEED_1000BASE_T,	FC2_DRIVER_OSB_NONE, 112 FC2_DROP_FRAMES, 114
111	FC2_EDGE_SENSING, 111
FC2_BUSSPEED_100BASE_T, 111	FC2_ERROR_BUFFER_TOO_SM-ALL, 113
FC2_BUSSPEED_10BASE_T, 111	
FC2_BUSSPEED_ANY, 111	FC2_ERROR_BUS_MASTER_FAI-
FC2_BUSSPEED_FORCE_32BITS,	LED, 113
111	FC2_ERROR_FAILED, 112

FC2_ERROR_FAILED_BUS_MAS-	FC2_ERROR_NOT_INTITIALIZED,
TER_CONNECTION, 112	112
FC2_ERROR_FAILED_GUID, 113	FC2_ERROR_NOT_IN_FORMAT7,
FC2_ERROR_FORCE_32BITS, 114	113
FC2_ERROR_IIDC_FAILED, 113	FC2_ERROR_NOT_SUPPORTED,
FC2_ERROR_IMAGE_CONSISTE-	113
NCY_ERROR, 113	FC2_ERROR_OK, 112
FC2_ERROR_IMAGE_CONVERSI-	FC2_ERROR_PROPERTY_FAILE-
ON_FAILED, 113	D, 113
FC2_ERROR_IMAGE_LIBRARY_F-	FC2_ERROR_PROPERTY_NOT_P-
AILURE, 113	RESENT, 113
FC2_ERROR_INCOMPATIBLE_D-	FC2_ERROR_READ_REGISTER
RIVER, 114	FAILED, 113
FC2_ERROR_INIT_FAILED, 112	FC2_ERROR_REGISTER_FAILED,
FC2_ERROR_INVALID_BUS_MAN-	113
AGER, 113	FC2_ERROR_STROBE_FAILED,
FC2_ERROR_INVALID_GENERAT-	113
ION, 113	FC2_ERROR_TIMEOUT, 113
FC2_ERROR_INVALID_MODE, 113	FC2 ERROR TRIGGER FAILED,
FC2_ERROR_INVALID_PACKET	113
SIZE, 113	FC2_ERROR_UNDEFINED, 112
FC2_ERROR_INVALID_PARAMET-	FC2 ERROR WRITE REGISTER-
ER, 112	FAILED, 113
FC2_ERROR_INVALID_SETTINGS,	FC2 FOCUS, 118
113	FC2_FRAMERATE_120, 114
FC2_ERROR_ISOCH_ALREADY	FC2_FRAMERATE_15, 114
STARTED, 113	FC2_FRAMERATE_1_875, 114
FC2_ERROR_ISOCH_BANDWIDT-	FC2_FRAMERATE_1_075, 114 FC2_FRAMERATE_240, 114
H_EXCEEDED, 113	
FC2_ERROR_ISOCH_FAILED, 113	FC2_FRAMERATE_30, 114
FC2_ERROR_ISOCH_NOT_STAR-	FC2_FRAMERATE_3_75, 114
TED, 113	FC2_FRAMERATE_60, 114
FC2_ERROR_ISOCH_RETRIEVE	FC2_FRAMERATE_7_5, 114
BUFFER_FAILED, 113	FC2_FRAMERATE_FORCE_32BIT-
FC2_ERROR_ISOCH_START_FAI-	S, 114
LED, 113	FC2_FRAMERATE_FORMAT7, 114
FC2_ERROR_ISOCH_STOP_FAIL-	FC2_FRAME_RATE, 118
ED, 113	FC2_FROM_FILE_EXT, 115
FC2_ERROR_ISOCH_SYNC_FAIL-	FC2_GAIN, 118
ED, 113	FC2_GAMMA, 118
FC2_ERROR_LOW_LEVEL_FAILU-	FC2_GRAB_MODE_FORCE_32BI-
RE, 113	TS, 115
FC2_ERROR_LUT_FAILED, 113	FC2_GRAB_TIMEOUT_FORCE
FC2_ERROR_MEMORY_ALLOCA-	32BITS, 115
TION_FAILED, 113	FC2_HQ_LINEAR, 111
FC2_ERROR_NOT_CONNECTED,	FC2_HUE, 118
112	FC2_IMAGE_FILE_FORMAT_FOR-
FC2_ERROR_NOT_FOUND, 113	CE_32BITS, 115
FC2_ERROR_NOT_IMPLEMENTE-	FC2_INTERFACE_GIGE, 116
D, 112	FC2_INTERFACE_IEEE1394, 115

FC2_INTERFACE_TYPE_FORCE	FC2_PAN, 118
32BITS, 116	FC2_PCIE_BUSSPEED_2_5, 117
FC2_INTERFACE_UNKNOWN, 116	FC2_PCIE_BUSSPEED_5_0, 117
FC2_INTERFACE_USB_2, 115	FC2_PCIE_BUSSPEED_FORCE
FC2 INTERFACE USB 3, 116	32BITS, 117
FC2 IPP, 111	FC2_PCIE_BUSSPEED_UNKNOW-
FC2_IRIS, 118	N, 117
FC2_JPEG, 115	FC2_PGM, 115
FC2_JPEG2000, 115	FC2_PIXEL_FORMAT_411YUV8,
FC2 MODE 0, 116	117
·	
FC2_MODE_1, 116	FC2_PIXEL_FORMAT_422YUV8,
FC2_MODE_10, 116	117
FC2_MODE_11, 116	FC2_PIXEL_FORMAT_422YUV8_J-
FC2_MODE_12, 116	PEG, 118
FC2_MODE_13, 116	FC2_PIXEL_FORMAT_444YUV8,
FC2_MODE_14, 116	117
FC2_MODE_15, 116	FC2_PIXEL_FORMAT_BGR, 117
FC2_MODE_16, 116	FC2_PIXEL_FORMAT_BGR16, 117
FC2_MODE_17, 116	FC2_PIXEL_FORMAT_BGRU, 117
FC2_MODE_18, 116	FC2 PIXEL FORMAT BGRU16,
FC2_MODE_19, 116	118
FC2_MODE_2, 116	FC2_PIXEL_FORMAT_MONO12,
FC2_MODE_20, 116	117
FC2_MODE_21, 116	FC2_PIXEL_FORMAT_MONO16,
FC2_MODE_22, 116	117
FC2_MODE_23, 116	FC2_PIXEL_FORMAT_MONO8,
FC2_MODE_24, 116	117
FC2_MODE_25, 116	FC2 PIXEL FORMAT RAW12, 117
FC2_MODE_26, 116	FC2 PIXEL FORMAT RAW16, 117
FC2_MODE_27, 116	FC2 PIXEL FORMAT RAW8, 117
FC2_MODE_28, 117	FC2 PIXEL FORMAT RGB, 117
FC2_MODE_29, 117	FC2_PIXEL_FORMAT_RGB16, 117
FC2_MODE_3, 116	FC2 PIXEL FORMAT RGB8, 117
FC2_MODE_30, 117	FC2 PIXEL FORMAT RGBU, 117
FC2_MODE_31, 117	FC2_PIXEL_FORMAT_S_MONO16,
FC2_MODE_4, 116	117
FC2 MODE 5, 116	FC2 PIXEL FORMAT S RGB16,
FC2 MODE 6, 116	117
FC2_MODE_7, 116	FC2_PNG, 115
FC2_MODE_8, 116	FC2_PPM, 115
FC2_MODE_8, 116 FC2_MODE_9, 116	FC2_FFM, TT3 FC2_PROPERTY TYPE FORCE -
FC2_MODE_FORCE_32BITS, 117	32BITS, 118
FC2_NEAREST_NEIGHBOR_FAS-	FC2_RAW, 115
T, 111	FC2_REMOVAL, 110
FC2_NO_COLOR_PROCESSING,	FC2_RIGOROUS, 111
111	FC2_SATURATION, 118
FC2_NUM_FRAMERATES, 114	FC2_SHARPNESS, 118
FC2_NUM_MODES, 117	FC2_SHUTTER, 118
FC2_NUM_PIXEL_FORMATS, 118	FC2_TEMPERATURE, 118
FC2_NUM_VIDEOMODES, 119	FC2_TIFF, 115

ECO TILT 110	110
FC2_TILT, 118	119
FC2_TIMEOUT_INFINITE, 115	FC2_VIDEOMODE_800x600Y16,
FC2_TIMEOUT_NONE, 115	119
FC2_TIMEOUT_UNSPECIFIED, 115	FC2_VIDEOMODE_800x600Y8, 119
FC2_TRIGGER_DELAY, 118	FC2_VIDEOMODE_800x600YU-
FC2_TRIGGER_MODE, 118	V422, 119
FC2_UNSPECIFIED_GRAB_MOD-	FC2_VIDEOMODE_FORCE_32BIT-
E, 115	S, 119
FC2_UNSPECIFIED_PIXEL_FOR-	FC2_VIDEOMODE_FORMAT7, 119
MAT, 118	FC2_WEIGHTED_DIRECTIONAL,
FC2_UNSPECIFIED_PROPERTY	112
 TYPE, 118	FC2_WHITE_BALANCE, 118
FC2_VIDEOMODE_1024x768RGB,	FC2_ZOOM, 118
119	FC2 ARRIVAL
FC2_VIDEOMODE_1024x768Y16,	Enumerations, 110
119	FC2_AUTO_EXPOSURE
FC2_VIDEOMODE_1024x768Y8,	Enumerations, 118
119	FC2_BANDWIDTH_ALLOCATION_FOR-
FC2 VIDEOMODE 1024x768YU-	CE 32BITS
<del>-</del>	<del>_</del>
V422, 119	Enumerations, 110
FC2_VIDEOMODE_1280x960RGB,	FC2_BANDWIDTH_ALLOCATION_OFF
119	Enumerations, 110
FC2_VIDEOMODE_1280x960Y16,	FC2_BANDWIDTH_ALLOCATION_ON
119	Enumerations, 110
FC2_VIDEOMODE_1280x960Y8,	FC2_BANDWIDTH_ALLOCATION_UNS-
119	PECIFIED
FC2_VIDEOMODE_1280x960YU-	Enumerations, 110
V422, 119	FC2_BANDWIDTH_ALLOCATION_UNS-
FC2_VIDEOMODE_1600x1200RG-	UPPORTED
B, 119	Enumerations, 110
FC2_VIDEOMODE_1600x1200Y16,	FC2_BMP
119	Enumerations, 115
FC2_VIDEOMODE_1600x1200Y8,	FC2_BRIGHTNESS
119	Enumerations, 118
FC2_VIDEOMODE_1600x1200YU-	FC2_BT_BGGR
V422, 119	Enumerations, 110
FC2_VIDEOMODE_160x120YU-	FC2_BT_FORCE_32BITS
V444, 118	Enumerations, 110
FC2_VIDEOMODE_320x240YU-	FC2_BT_GBRG
 V422, 118	Enumerations, 110
FC2 VIDEOMODE 640x480RGB,	FC2_BT_GRBG
119	Enumerations, 110
FC2 VIDEOMODE 640x480Y16,	FC2_BT_NONE
119	Enumerations, 110
FC2_VIDEOMODE_640x480Y8, 119	FC2 BT RGGB
FC2_VIDEOMODE_640x480YU-	Enumerations, 110
V411, 119	FC2 BUFFER FRAMES
FC2_VIDEOMODE_640x480YU-	
	Enumerations, 114
V422, 119	FC2_BUSSPEED_10000BASE_T
FC2_VIDEOMODE_800x600RGB,	Enumerations, 111

FC2_BUSSPEED_1000BASE_T	FC2_DRIVER_1394_JUJU
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_100BASE_T	FC2_DRIVER_1394_PRO
Enumerations, 111	Enumerations, 112
FC2 BUSSPEED 10BASE T	FC2_DRIVER_1394_RAW1394
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_ANY	FC2_DRIVER_1394_VIDEO1394
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_FORCE_32BITS	FC2_DRIVER_FORCE_32BITS
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S100	FC2_DRIVER_GIGE_FILTER
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S1600	FC2_DRIVER_GIGE_LWF
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S200	FC2_DRIVER_GIGE_NONE
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S3200	FC2_DRIVER_GIGE_PRO
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S400	FC2_DRIVER_UNKNOWN
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S480	FC2_DRIVER_USB3_PRO
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S5000	FC2_DRIVER_USB_CAM
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_S800	FC2_DRIVER_USB_NONE
Enumerations, 111	Enumerations, 112
FC2_BUSSPEED_SPEED_UNKNOWN	FC2_DROP_FRAMES
Enumerations, 111	Enumerations, 114
FC2_BUSSPEED_S_FASTEST	FC2_EDGE_SENSING
Enumerations, 111	Enumerations, 111
FC2_BUS_RESET	FC2_ERROR_BUFFER_TOO_SMALL
Enumerations, 110	Enumerations, 113
FC2_BYTE_ORDER_BIG_ENDIAN	FC2_ERROR_BUS_MASTER_FAILED
FlyCapture2Defs_C.h, 216	Enumerations, 113
FC2_BYTE_ORDER_FORCE_32BITS	FC2 ERROR FAILED
FlyCapture2Defs_C.h, 216	Enumerations, 112
FC2_BYTE_ORDER_LITTLE_ENDIAN	FC2_ERROR_FAILED_BUS_MASTER
FlyCapture2Defs_C.h, 216	CONNECTION
FC2_CALLBACK_TYPE_FORCE_32BIT-	Enumerations, 112
S	FC2_ERROR_FAILED_GUID
Enumerations, 110	Enumerations, 113
FC2_COLOR_PROCESSING_ALGORIT-	FC2_ERROR_FORCE_32BITS
HM_FORCE_32BITS	Enumerations, 114
Enumerations, 112	FC2 ERROR IIDC FAILED
FC2_DEFAULT	Enumerations, 113
Enumerations, 111	FC2_ERROR_IMAGE_CONSISTENCY_
FC2_DIRECTIONAL	ERROR
Enumerations, 111	Enumerations, 113
FC2_DRIVER_1394_CAM	FC2_ERROR_IMAGE_CONVERSION
Enumerations, 112	FAILED

Enumerations, 113	Enumerations, 113
FC2_ERROR_IMAGE_LIBRARY_FAILU- RE	FC2_ERROR_NOT_IMPLEMENTED Enumerations, 112
Enumerations, 113	FC2_ERROR_NOT_INTITIALIZED
FC2_ERROR_INCOMPATIBLE_DRIVER	Enumerations, 112 FC2_ERROR_NOT_IN_FORMAT7
Enumerations, 114 FC2_ERROR_INIT_FAILED	Enumerations, 113
Enumerations, 112	FC2_ERROR_NOT_SUPPORTED
FC2_ERROR_INVALID_BUS_MANAGE-	Enumerations, 113
Enumerations, 113	FC2_ERROR_OK Enumerations, 112
FC2_ERROR_INVALID_GENERATION	FC2_ERROR_PROPERTY_FAILED
Enumerations, 113 FC2_ERROR_INVALID_MODE	Enumerations, 113 FC2_ERROR_PROPERTY_NOT_PRES-
Enumerations, 113	ENT
FC2_ERROR_INVALID_PACKET_SIZE	Enumerations, 113
Enumerations, 113 FC2 ERROR INVALID PARAMETER	FC2_ERROR_READ_REGISTER_FAIL- ED
Enumerations, 112	Enumerations, 113
FC2_ERROR_INVALID_SETTINGS	FC2_ERROR_REGISTER_FAILED
Enumerations, 113 FC2_ERROR_ISOCH_ALREADY_STAR-	Enumerations, 113 FC2_ERROR_STROBE_FAILED
TED	Enumerations, 113
Enumerations, 113	FC2_ERROR_TIMEOUT
FC2_ERROR_ISOCH_BANDWIDTH_E- XCEEDED	Enumerations, 113 FC2_ERROR_TRIGGER_FAILED
Enumerations, 113	Enumerations, 113
FC2_ERROR_ISOCH_FAILED	FC2_ERROR_UNDEFINED
Enumerations, 113	Enumerations, 112
FC2_ERROR_ISOCH_NOT_STARTED Enumerations, 113	FC2_ERROR_WRITE_REGISTER_FAIL- ED
FC2_ERROR_ISOCH_RETRIEVE_BUF-	Enumerations, 113
FER_FAILED	FC2_FOCUS
Enumerations, 113 FC2_ERROR_ISOCH_START_FAILED	Enumerations, 118 FC2_FRAMERATE_120
Enumerations, 113	Enumerations, 114
FC2_ERROR_ISOCH_STOP_FAILED	FC2_FRAMERATE_15
Enumerations, 113 FC2_ERROR_ISOCH_SYNC_FAILED	Enumerations, 114 FC2_FRAMERATE_1_875
Enumerations, 113	Enumerations, 114
FC2_ERROR_LOW_LEVEL_FAILURE	FC2_FRAMERATE_240
Enumerations, 113 FC2_ERROR_LUT_FAILED	Enumerations, 114 FC2_FRAMERATE_30
Enumerations, 113	Enumerations, 114
FC2_ERROR_MEMORY_ALLOCATION-	FC2_FRAMERATE_3_75
_FAILED Enumerations, 113	Enumerations, 114 FC2_FRAMERATE_60
FC2_ERROR_NOT_CONNECTED	Enumerations, 114
Enumerations, 112	FC2_FRAMERATE_7_5
FC2_ERROR_NOT_FOUND	Enumerations, 114

FC2_FRAMERATE_FORCE_32BITS	FC2_LINUX_X86
Enumerations, 114 FC2 FRAMERATE FORMAT7	FlyCapture2Defs_C.h, 217 FC2_MAC
Enumerations, 114	FlyCapture2Defs_C.h, 217
FC2_FRAME_RATE	FC2_MODE_0
Enumerations, 118	Enumerations, 116
FC2_FROM_FILE_EXT	FC2_MODE_1
Enumerations, 115	Enumerations, 116
FC2_GAIN	FC2_MODE_10
Enumerations, 118	Enumerations, 116
FC2_GAMMA	FC2_MODE_11
Enumerations, 118	Enumerations, 116
FC2_GRAB_MODE_FORCE_32BITS	FC2_MODE_12
Enumerations, 115	Enumerations, 116
FC2_GRAB_TIMEOUT_FORCE_32BITS	FC2_MODE_13
Enumerations, 115	Enumerations, 116
FC2_HEARTBEAT	FC2_MODE_14
GigE specific enumerations, 120	Enumerations, 116
FC2_HEARTBEAT_TIMEOUT	FC2_MODE_15
GigE specific enumerations, 120	Enumerations, 116
FC2_HQ_LINEAR	FC2_MODE_16
Enumerations, 111	Enumerations, 116
FC2_HUE	FC2_MODE_17 Enumerations, 116
Enumerations, 118 FC2_IMAGE_FILE_FORMAT_FORCE	FC2_MODE_18
32BITS	Enumerations, 116
Enumerations, 115	FC2_MODE_19
FC2_INTERFACE_GIGE	Enumerations, 116
Enumerations, 116	FC2_MODE_2
FC2_INTERFACE_IEEE1394	Enumerations, 116
Enumerations, 115	FC2_MODE_20
FC2_INTERFACE_TYPE_FORCE_32BI-	Enumerations, 116
TS	FC2_MODE_21
Enumerations, 116	Enumerations, 116
FC2_INTERFACE_UNKNOWN	FC2_MODE_22
Enumerations, 116	Enumerations, 116
FC2_INTERFACE_USB_2	FC2_MODE_23
Enumerations, 115	Enumerations, 116
FC2_INTERFACE_USB_3	FC2_MODE_24
Enumerations, 116	Enumerations, 116
FC2_IPP	FC2_MODE_25
Enumerations, 111	Enumerations, 116
FC2_IRIS	FC2_MODE_26
Enumerations, 118	Enumerations, 116
FC2_JPEG	FC2_MODE_27
Enumerations, 115 FC2 JPEG2000	Enumerations, 116 FC2 MODE 28
Enumerations, 115	Enumerations, 117
FC2 LINUX X64	FC2 MODE 29
FlyCapture2Defs_C.h, 217	Enumerations, 117
· ., oapia. o== o.o_o, =	, 111

FC2_MODE_3	Enumerations, 117
Enumerations, 116	FC2 PIXEL FORMAT 422YUV8 JPEG
FC2_MODE_30	Enumerations, 118
Enumerations, 117	FC2 PIXEL FORMAT 444YUV8
	Enumerations, 117
FC2_MODE_31	FC2 PIXEL FORMAT BGR
Enumerations, 117 FC2_MODE_4	Enumerations, 117
	FC2 PIXEL FORMAT BGR16
Enumerations, 116 FC2_MODE_5	
	Enumerations, 117 FC2 PIXEL FORMAT BGRU
Enumerations, 116	
FC2_MODE_6	Enumerations, 117
Enumerations, 116	FC2_PIXEL_FORMAT_BGRU16
FC2_MODE_7	Enumerations, 118
Enumerations, 116	FC2_PIXEL_FORMAT_MONO12
FC2_MODE_8	Enumerations, 117
Enumerations, 116	FC2_PIXEL_FORMAT_MONO16
FC2_MODE_9	Enumerations, 117
Enumerations, 116	FC2_PIXEL_FORMAT_MONO8
FC2_MODE_FORCE_32BITS	Enumerations, 117
Enumerations, 117	FC2_PIXEL_FORMAT_RAW12
FC2_NEAREST_NEIGHBOR_FAST	Enumerations, 117
Enumerations, 111	FC2_PIXEL_FORMAT_RAW16
FC2_NO_COLOR_PROCESSING	Enumerations, 117
Enumerations, 111	FC2_PIXEL_FORMAT_RAW8
FC2_NUM_FRAMERATES	Enumerations, 117
Enumerations, 114	FC2_PIXEL_FORMAT_RGB
FC2_NUM_MODES	Enumerations, 117
Enumerations, 117	FC2_PIXEL_FORMAT_RGB16
FC2_NUM_PIXEL_FORMATS	Enumerations, 117
Enumerations, 118	FC2_PIXEL_FORMAT_RGB8
FC2_NUM_VIDEOMODES	Enumerations, 117
Enumerations, 119	FC2_PIXEL_FORMAT_RGBU
FC2_OSTYPE_FORCE_32BITS	Enumerations, 117
FlyCapture2Defs_C.h, 217	FC2_PIXEL_FORMAT_S_MONO16
FC2_PAN	Enumerations, 117
Enumerations, 118	FC2_PIXEL_FORMAT_S_RGB16
FC2_PCIE_BUSSPEED_2_5	Enumerations, 117
Enumerations, 117	FC2_PNG
FC2_PCIE_BUSSPEED_5_0	Enumerations, 115
Enumerations, 117	FC2_PPM
FC2_PCIE_BUSSPEED_FORCE_32BIT-	Enumerations, 115
S	FC2_PROPERTY_TYPE_FORCE_32BI-
Enumerations, 117	TS
FC2_PCIE_BUSSPEED_UNKNOWN	Enumerations, 118
Enumerations, 117	FC2_RAW
FC2_PGM	Enumerations, 115
Enumerations, 115	FC2_REMOVAL
FC2_PIXEL_FORMAT_411YUV8	Enumerations, 110
Enumerations, 117	FC2_RIGOROUS
FC2_PIXEL_FORMAT_422YUV8	Enumerations, 111

FC2_SATURATION	FC2_TRIGGER_DELAY
Enumerations, 118	Enumerations, 118
FC2_SHARPNESS	FC2_TRIGGER_MODE
Enumerations, 118	Enumerations, 118
FC2_SHUTTER	FC2_UNKNOWN_OS
Enumerations, 118	FlyCapture2Defs_C.h, 217
FC2_STATISTICS_BLUE	FC2_UNSPECIFIED_GRAB_MODE
FlyCapture2Defs_C.h, 217	Enumerations, 115
FC2_STATISTICS_FORCE_32BITS	FC2_UNSPECIFIED_PIXEL_FORMAT
FlyCapture2Defs_C.h, 217	Enumerations, 118
FC2_STATISTICS_GREEN	FC2_UNSPECIFIED_PROPERTY_TYPE
FlyCapture2Defs_C.h, 217	Enumerations, 118
FC2_STATISTICS_GREY	FC2_VIDEOMODE_1024x768RGB
FlyCapture2Defs_C.h, 217	Enumerations, 119
FC2_STATISTICS_HUE	FC2_VIDEOMODE_1024x768Y16
FlyCapture2Defs_C.h, 217	Enumerations, 119
FC2_STATISTICS_LIGHTNESS	FC2_VIDEOMODE_1024x768Y8
FlyCapture2Defs_C.h, 217	Enumerations, 119
FC2_STATISTICS_RED	FC2_VIDEOMODE_1024x768YUV422
FlyCapture2Defs_C.h, 217	Enumerations, 119
FC2_STATISTICS_SATURATION	FC2_VIDEOMODE_1280x960RGB
FlyCapture2Defs_C.h, 217	Enumerations, 119
FC2_TEMPERATURE	FC2_VIDEOMODE_1280x960Y16
Enumerations, 118	Enumerations, 119
FC2_TIFF	FC2_VIDEOMODE_1280x960Y8
Enumerations, 115	Enumerations, 119
FC2_TIFF_ADOBE_DEFLATE	FC2_VIDEOMODE_1280x960YUV422
Image saving structures., 126	Enumerations, 119
FC2_TIFF_CCITTFAX3	FC2_VIDEOMODE_1600x1200RGB
Image saving structures., 126	Enumerations, 119
FC2_TIFF_CCITTFAX4	FC2_VIDEOMODE_1600x1200Y16
Image saving structures., 126	Enumerations, 119
FC2_TIFF_DEFLATE	FC2_VIDEOMODE_1600x1200Y8
Image saving structures., 126	Enumerations, 119
FC2_TIFF_JPEG	FC2_VIDEOMODE_1600x1200YUV422
Image saving structures., 126	Enumerations, 119
FC2_TIFF_LZW	FC2_VIDEOMODE_160x120YUV444
Image saving structures., 126	Enumerations, 118
FC2_TIFF_NONE	FC2_VIDEOMODE_320x240YUV422
Image saving structures., 126	Enumerations, 118
FC2_TIFF_PACKBITS	FC2_VIDEOMODE_640x480RGB
Image saving structures., 126	Enumerations, 119
FC2_TILT	FC2_VIDEOMODE_640x480Y16
Enumerations, 118	Enumerations, 119
FC2_TIMEOUT_INFINITE	FC2_VIDEOMODE_640x480Y8
Enumerations, 115	Enumerations, 119
FC2_TIMEOUT_NONE	FC2_VIDEOMODE_640x480YUV411
Enumerations, 115	Enumerations, 119
FC2_TIMEOUT_UNSPECIFIED	FC2_VIDEOMODE_640x480YUV422
Enumerations, 115	Enumerations, 119

FC2_VIDEOMODE_800x600RGB	FC2_UNKNOWN_OS, 217
Enumerations, 119	FC2_WINDOWS_X64, 217
FC2_VIDEOMODE_800x600Y16	FC2_WINDOWS_X86, 217
Enumerations, 119	NODE, 217
FC2_VIDEOMODE_800x600Y8	NOT_CONNECTED, 217
Enumerations, 119	GigE specific enumerations
FC2_VIDEOMODE_800x600YUV422	FC2_HEARTBEAT, 120
Enumerations, 119	FC2_HEARTBEAT_TIMEOUT, 120
FC2_VIDEOMODE_FORCE_32BITS	PACKET_DELAY, 120
Enumerations, 119	PACKET_SIZE, 120
FC2_VIDEOMODE_FORMAT7	Image saving structures.
Enumerations, 119	FC2_TIFF_ADOBE_DEFLATE, 126
FC2_WEIGHTED_DIRECTIONAL	FC2_TIFF_CCITTFAX3, 126
Enumerations, 112	FC2_TIFF_CCITTFAX4, 126
FC2_WHITE_BALANCE	FC2_TIFF_DEFLATE, 126
Enumerations, 118	FC2_TIFF_JPEG, 126
FC2_WINDOWS_X64	FC2_TIFF_LZW, 126
FlyCapture2Defs_C.h, 217	FC2_TIFF_NONE, 126
FC2_WINDOWS_X86	FC2_TIFF_PACKBITS, 126
FlyCapture2Defs_C.h, 217	MultiSyncLibraryDefs_C.h
FC2_ZOOM	SYNC_ERROR_ALREADY_START-
Enumerations, 118	ED, 229
FlyCapture2Defs_C.h	SYNC_ERROR_ALREADY_STOP-
BUS, 217	PED, 229
CAMERA, 217	SYNC_ERROR_CONTEXT_NOT_I-
COMPUTER, 217	NITIALIZED, 229
CONNECTED_TO_CHILD, 217	SYNC_ERROR_FAILED, 229
CONNECTED_TO_PARENT, 217	SYNC_ERROR_OK, 229
FC2_BYTE_ORDER_BIG_ENDIAN,	SYNC_ERROR_UNKNOWN_ERR-
216	OR, 229
FC2_BYTE_ORDER_FORCE_32BI-	SYNC_MESSAGE_BUS_RESET,
TS, 216	229
FC2_BYTE_ORDER_LITTLE_ENDI-	SYNC_MESSAGE_DEVICE_ERRO-
AN, 216	R, 229
FC2_LINUX_X64, 217	SYNC_MESSAGE_FAILED, 229
FC2_LINUX_X86, 217	SYNC_MESSAGE_NOMASTER,
FC2_MAC, 217	229
FC2_OSTYPE_FORCE_32BITS,	SYNC_MESSAGE_NOT_ENOUGH-
217	_DEVICES, 229
FC2_STATISTICS_BLUE, 217	SYNC_MESSAGE_NOT_INITIALIZ-
FC2_STATISTICS_FORCE_32BIT-	ED, 229
S, 217	SYNC_MESSAGE_OK, 229
FC2_STATISTICS_GREEN, 217	SYNC_MESSAGE_STARTED, 229
FC2_STATISTICS_GREY, 217	SYNC_MESSAGE_STOPPED, 229
FC2_STATISTICS_HUE, 217	SYNC_MESSAGE_SYNCING, 229
FC2_STATISTICS_LIGHTNESS,	SYNC_MESSAGE_THREAD_ERR-
217	OR, 229
FC2_STATISTICS_RED, 217	SYNC_MESSAGE_UNKNOWN_E-
FC2_STATISTICS_SATURATION,	RROR, 229
217	NODE

FlyCapture2Defs_C.h, 217	fc2FireBusReset, 15
NOT_CONNECTED	fc2ForceAllIPAddressesAutomatically
FlyCapture2Defs_C.h, 217	16
PACKET DELAY	fc2ForceIPAddressAutomatically, 16
GigE specific enumerations, 120	fc2ForceIPAddressToCamera, 16
PACKET SIZE	fc2GetCameraFromIPAddress, 17
GigE specific enumerations, 120	fc2GetCameraFromIndex, 17
SYNC_ERROR_ALREADY_STARTED	fc2GetCameraFromSerialNumber,
MultiSyncLibraryDefs_C.h, 229	17
SYNC_ERROR_ALREADY_STOPPED	fc2GetCameraSerialNumberFrom-
MultiSyncLibraryDefs_C.h, 229	Index, 18
SYNC_ERROR_CONTEXT_NOT_INITI-	fc2GetDeviceFromIndex, 18
ALIZED	fc2GetInterfaceTypeFromGuid, 18
MultiSyncLibraryDefs_C.h, 229	fc2GetNumOfCameras, 19
SYNC_ERROR_FAILED	fc2GetNumOfDevices, 19
MultiSyncLibraryDefs_C.h, 229	fc2GetTopology, 20
SYNC_ERROR_OK	fc2GetUsbLinkInfo, 20
MultiSyncLibraryDefs_C.h, 229	fc2GetUsbPortStatus, 20
SYNC_ERROR_UNKNOWN_ERROR	fc2lsCameraControlable, 21
MultiSyncLibraryDefs_C.h, 229	fc2ReadPhyRegister, 21
SYNC_MESSAGE_BUS_RESET	fc2RegisterCallback, 21
MultiSyncLibraryDefs_C.h, 229	fc2RescanBus, 22
SYNC_MESSAGE_DEVICE_ERROR	fc2UnregisterCallback, 22
MultiSyncLibraryDefs_C.h, 229	fc2WritePhyRegister, 22
SYNC_MESSAGE_FAILED	Connection and Image Retrieval, 24
MultiSyncLibraryDefs_C.h, 229	fc2Connect, 25
SYNC_MESSAGE_NOMASTER	fc2Disconnect, 25
MultiSyncLibraryDefs_C.h, 229	fc2GetConfiguration, 25
SYNC_MESSAGE_NOT_ENOUGH_DE-	fc2IsConnected, 26
VICES	fc2RetrieveBuffer, 26
MultiSyncLibraryDefs_C.h, 229	fc2SetCallback, 27
SYNC_MESSAGE_NOT_INITIALIZED	fc2SetConfiguration, 27
MultiSyncLibraryDefs_C.h, 229	fc2SetUserBuffers, 28
SYNC MESSAGE OK	fc2StartCapture, 28
MultiSyncLibraryDefs_C.h, 229	fc2StartCaptureCallback, 29
SYNC MESSAGE STARTED	fc2StartSyncCapture, 29
MultiSyncLibraryDefs_C.h, 229	fc2StartSyncCaptureCallback, 30
SYNC MESSAGE STOPPED	fc2StopCapture, 30
MultiSyncLibraryDefs_C.h, 229	fc2WaitForBufferEvent, 31
SYNC MESSAGE SYNCING	DCAM Formats, 58
MultiSyncLibraryDefs_C.h, 229	fc2GetVideoModeAndFrameRate, 58
SYNC MESSAGE THREAD ERROR	fc2GetVideoModeAndFrameRate-
MultiSyncLibraryDefs_C.h, 229	Info, 59
SYNC_MESSAGE_UNKNOWN_ERROR	fc2SetVideoModeAndFrameRate, 59
MultiSyncLibraryDefs_C.h, 229	Enumerations, 107
BOOL	fc2BandwidthAllocation, 109
MultiSyncLibraryDefs_C.h, 228	fc2BayerTileFormat, 110
TypeDefs, 105	fc2BusCallbackType, 110
Bus Manager Operation, 13	fc2BusSpeed, 110
	•
fc2DiscoverGigECameras, 15	fc2ColorProcessingAlgorithm, 111

fc2DriverType, 112	fc2lsVisible, 220
fc2Error, 112	fc2Show, 220
fc2FrameRate, 114	fc2ShowModal, 220
fc2GrabMode, 114	FlyCapture2Internal_C.h, 221
fc2GrabTimeout, 115	IsContextValid, 221
fc2ImageFileFormat, 115	IsGuiContextValid, 221
fc2InterfaceType, 115	SyncCppImageToStruct, 221
fc2Mode, 116	FlyCapture2Platform_C.h, 221
fc2PCleBusSpeed, 117	FlyCapture2Private_C.h, 222
fc2PixelFormat, 117	GetInternal, 222
fc2PropertyType, 118	FlyCapture2VideoDefs_C.h, 223
fc2VideoMode, 118	FlyCapture2Video_C.h, 222
EventCallbackFcn	FlyCapture2_C.h, 195
fc2EventOptions, 152	ResetStats, 210
EventData	fc2CreateContext, 207
fc2EventCallbackData, 150	fc2CreateGigEContext, 207
EventDataSize	fc2DeregisterAllEvents, 208
fc2EventCallbackData, 150	fc2DeregisterEvent, 208
EventID	fc2DestroyContext, 208
fc2EventCallbackData, 151	fc2GetCycleTime, 209
EventName	fc2GetStats, 209
fc2EventCallbackData, 151	fc2RegisterAllEvents, 209
fc2EventOptions, 152	fc2RegisterEvent, 210
EventTimestamp	Format7, 60
fc2EventCallbackData, 151	fc2GetFormat7Configuration, 60
EventUserData	fc2GetFormat7Info, 61
fc2EventCallbackData, 151	fc2SetFormat7Configuration, 61
fc2EventOptions, 152	fc2SetFormat7ConfigurationPacket,
EventUserDataSize	61
fc2EventCallbackData, 151	fc2ValidateFormat7Settings, 62
fc2EventOptions, 152	GPIOPinState
FALSE	fc2EmbeddedImageInfo, 149
MultiSyncLibraryDefs_C.h, 228	GVCP Register Operation, 63
TypeDefs, 105	fc2ReadGVCPMemory, 63
FULL_32BIT_VALUE	fc2ReadGVCPRegister, 64
MultiSyncLibraryDefs_C.h, 228	fc2ReadGVCPRegisterBlock, 64
TypeDefs, 105	fc2WriteGVCPMemory, 64
FlyCapture2Defs_C.h, 210	fc2WriteGVCPRegister, 65
fc2ByteOrder, 216	fc2WriteGVCPRegisterBlock, 65
fc2NodeType, 216	fc2WriteGVCPRegisterBroadcast, 65
fc2OSType, 217	General Purpose Input / Output, 35
fc2PortType, 217	fc2GetGPIOPinDirection, 35
fc2StatisticsChannel, 217	fc2SetGPIOPinDirection, 35
FlyCapture2GUI_C.h, 218	fc2SetGPIOPinDirectionBroadcast,
fc2CreateGUIContext, 218	36
fc2DestroyGUIContext, 218	GetInternal
fc2Disonnect, 219	FlyCapture2Private_C.h, 222
fc2GUIConnect, 219	GigE image binning settings, 72
fc2GUIDisconnect, 219	fc2GetGigEImageBinningSettings,
fc2Hide, 220	72
•	

fc2SetGigEImageBinningSettings,	fc2GetChannelPixelValueRange, 89 fc2GetChannelRange, 89
GigE image settings, 69	fc2GetChannelStatus, 90
fc2GetGigEImageSettings, 69	fc2GetImageStatistics, 90
fc2GetGigEImageSettingsInfo, 70	fc2ImageStatisticsDisableAll, 91
fc2GetGigEImagingMode, 70	fc2ImageStatisticsEnableAll, 91
fc2QueryGigEImagingMode, 70	fc2ImageStatisticsEnableGreyOnly,
fc2SetGigEImageSettings, 70	92
fc2SetGigEImagingMode, 71	fc2ImageStatisticsEnableHSLOnly,
GigE image stream configuration, 74	92
fc2GetGigEConfig, 74	fc2ImageStatisticsEnableRGBOnly,
fc2GetGigEStreamChannelInfo, 75	92
fc2GetNumStreamChannels, 75	fc2SetChannelStatus, 93
fc2SetGigEConfig, 75	Image saving structures., 125
fc2SetGigEStreamChannelInfo, 76	fc2AsyncCommandCallback, 126
GigE property manipulation, 67	fc2BusEventCallback, 126
fc2DiscoverGigEPacketSize, 67	fc2CallbackHandle, 126
fc2GetGigEProperty, 67	fc2CameraEventCallback, 126
fc2SetGigEProperty, 68	fc2ImageEventCallback, 126
GigE specific enumerations, 120	fc2TIFFCompressionMethod, 126
fc2GigEPropertyType, 120	Information and Properties, 32
GigE specific structures, 123	fc2GetCameraInfo, 32
IIDC specific structures, 124	fc2GetProperty, 32
Image Operation, 77	fc2GetPropertyInfo, 33
fc2CalculateImageStatistics, 78	fc2SetProperty, 34
fc2ConvertImage, 79	fc2SetPropertyBroadcast, 34
fc2ConvertImageTo, 79	IsContextValid
fc2CreateImage, 79	FlyCapture2Internal_C.h, 221
fc2DestroyImage, 80	IsGuiContextValid
fc2DetermineBitsPerPixel, 80	FlyCapture2Internal_C.h, 221
fc2GetDefaultColorProcessing, 80	Licensing.dox, 223
fc2GetDefaultOutputFormat, 81	Look Up Table, 46
fc2GetImageColorProcessing, 81	fc2EnableLUT, 46
fc2GetImageData, 81	fc2GetActiveLUTBank, 47
fc2GetImageDimensions, 82	fc2GetLUTBankInfo, 47
fc2GetImageMetadata, 82	fc2GetLUTChannel, 47
fc2GetImageTimeStamp, 82	fc2GetLUTInfo, 48
fc2SaveImage, 83	fc2SetActiveLUTBank, 48
fc2SaveImageWithOption, 83	fc2SetLUTChannel, 49
fc2SetDefaultColorProcessing, 83	MAX_STRING_LENGTH
fc2SetDefaultOutputFormat, 84	TypeDefs, 105
fc2SetImageColorProcessing, 84	Memory Channels, 50
fc2SetImageData, 84	fc2GetEmbeddedImageInfo, 50
fc2SetImageDimensions, 85	fc2GetMemoryChannell, 51
Image Statistics Operation, 86	fc2GetMemoryChannelInfo, 51
fc2CreateImageStatistics, 87	fc2RestoreFromMemoryChannel, 51
fc2DestroyImageStatistics, 87	fc2SaveToMemoryChannel, 52
fc2GetChannelHistogram, 88 fc2GetChannelMean, 88	fc2SetEmbeddedImageInfo, 52 MultiSyncLibraryDefs_C.h, 227
fc2GetChannelNumPixelValues, 88	BOOL, 228
102061011a111161114U111F1XEIValues, 00	DOOL, 220

FALSE, 228	fc2TopologyNodeAssignGuidTo-
TRUE, 228	NodeEx, 97
syncContext, 228	fc2TopologyNodeGetChild, 97
syncError, 229	fc2TopologyNodeGetDeviceId, 98
syncMessage, 229	fc2TopologyNodeGetGuid, 98
MultiSyncLibraryPlatform_C.h, 229	fc2TopologyNodeGetInterfaceType,
MultiSyncLibrary_C.h, 223	98
syncCreateContext, 224	fc2TopologyNodeGetNodeType, 99
syncDestroyContext, 224	fc2TopologyNodeGetNumChildren,
syncDisableCrossPCSynchronization,	99
225	fc2TopologyNodeGetNumPorts, 100
syncEnableCrossPCSynchronization,	fc2TopologyNodeGetPortType, 100
225	Trigger, 37
syncGetStatus, 225	fc2FireSoftwareTrigger, 38
syncGetTimeSinceSynced, 226	fc2FireSoftwareTriggerBroadcast, 38
synclsTimingBusConnected, 226	fc2GetTriggerDelay, 38
syncQueryCrossPCSynchronization-	fc2GetTriggerDelayInfo, 39
Setting, 226	fc2GetTriggerMode, 39
syncRescanMasterTimingBus, 227	fc2GetTriggerModeInfo, 40
syncStart, 227	fc2SetTriggerDelay, 40
syncStop, 227	fc2SetTriggerDelayBroadcast, 41
ROIPosition	fc2SetTriggerMode, 41
fc2EmbeddedImageInfo, 149	fc2SetTriggerModeBroadcast, 42
Register Operation, 54	TypeDefs, 105
fc2GetRegisterString, 54	BOOL, 105
fc2ReadRegister, 54	FALSE, 105
fc2ReadRegisterBlock, 55	FULL_32BIT_VALUE, 105
fc2WriteRegister, 55	MAX_STRING_LENGTH, 105
fc2WriteRegisterBlock, 56	TRUE, 105
fc2WriteRegisterBroadcast, 56	fc2Context, 105
ResetStats	fc2GuiContext, 106
FlyCapture2_C.h, 210	fc2ImageImpl, 106
Strobe, 43	fc2ImageStatisticsContext, 106
fc2GetStrobe, 43	fc2TopologyNodeContext, 106
fc2GetStrobeInfo, 44	fc2VideoContext, 106
fc2SetStrobe, 44	Utilities, 101
fc2SetStrobeBroadcast, 44	fc2CheckDriver, 101
Structures, 121	fc2ErrorToDescription, 102
SyncCppImageToStruct	fc2GetDriverDeviceName, 102
FlyCapture2Internal_C.h, 221	fc2GetLibraryVersion, 102
TRUE	fc2GetSystemInfo, 102
MultiSyncLibraryDefs_C.h, 228	fc2LaunchBrowser, 103
TypeDefs, 105	fc2LaunchCommand, 103
TopologyNode Operation, 94	fc2LaunchCommandAsync, 103
fc2CreateTopologyNode, 95	fc2LaunchHelp, 104
fc2DestroyTopologyNode, 95	Video Recording Operation, 127
fc2TopologyNodeAddChild, 96	fc2VideoAVIOpen, 128
fc2TopologyNodeAddPortType, 96	fc2VideoAppend, 127
fc2TopologyNodeAssignGuidTo-	fc2VideoClose, 128
Node, 96	fc2VideoCreate, 128
	•

fc2VideoDestroy, 129	fc2CameraStats, 141
fc2VideoBestroy, 129	cameraPowerUp
fc2VideoMJPGOpen, 130	fc2CameraStats, 141
fc2VideoSetMaximumSize, 130	cameraVoltages
Video saving structures., 131	fc2CameraStats, 141
video saving structures., 131	
absControl	ccpStatus
fc2TriggerDelay, 185	fc2CameraInfo, 137
absMax	chipIdHi
fc2TriggerDelayInfo, 188	fc2ConfigROM, 146
absMin	chipIdLo
fc2TriggerDelayInfo, 188	fc2ConfigROM, 146
absValSupported	cols
fc2TriggerDelayInfo, 188	fc2Image, 166
absValue	compression
fc2TriggerDelay, 185	fc2TIFFOption, 183
applicationIPAddress	compressionLevel
fc2CameraInfo, 137	fc2PNGOption, 176
applicationPort	configROM
fc2CameraInfo, 137	fc2CameraInfo, 137
asyncBusSpeed	cpuDescription
fc2Config, 143	fc2SystemInfo, 181
autoManualMode	cycleCount
fc2TriggerDelay, 186	fc2TimeStamp, 184
autoSupported	cycleOffset
fc2TriggerDelayInfo, 188	fc2TimeStamp, 184
available	cycleSeconds
fc2EmbeddedImageInfoProperty,	fc2TimeStamp, 184
149	dataSize
	fc2Image, 166
bandwidthAllocation	defaultGateway
fc2Config, 143	fc2CameraInfo, 137
bayerFormat	
fc2Image, 166	delay
bayerTileFormat	fc2StrobeControl, 178
fc2CameraInfo, 137	destinationIpAddress
binaryFile	fc2GigEStreamChannel, 163
fc2PGMOption, 175	doNotFragment
fc2PPMOption, 177	fc2GigEStreamChannel, 164
bitrate	driverList
fc2H264Option, 165	fc2SystemInfo, 181
brightness	driverName
fc2EmbeddedImageInfo, 149	fc2CameraInfo, 137
build	driverType
fc2Version, 193	fc2CameraInfo, 137
busNumber	duration
fc2CameraInfo, 137	fc2StrobeControl, 178
byteOrder	amb add adDviabta
fc2SystemInfo, 181	embeddedBrightness
aamara Curranta	fc2ImageMetadata, 167
cameraCurrents	embeddedExposure

fc2ImageMetadata, 167	fc2CameraInfo, 134
embeddedFrameCounter	applicationIPAddress, 137
fc2ImageMetadata, 167	applicationPort, 137
embeddedGPIOPinState	bayerTileFormat, 137
fc2ImageMetadata, 167	busNumber, 137
embeddedGain	ccpStatus, 137
fc2ImageMetadata, 167	configROM, 137
embeddedROIPosition	defaultGateway, 137
fc2ImageMetadata, 167	driverName, 137
embeddedShutter	driverType, 137
fc2ImageMetadata, 168	firmwareBuildTime, 137
embeddedStrobePattern	firmwareVersion, 137
fc2ImageMetadata, 168	gigEMajorVersion, 138
embeddedTimeStamp	gigEMinorVersion, 138
fc2ImageMetadata, 168	iidcVer, 138
embeddedWhiteBalance	interfaceType, 138
	ipAddress, 138
fc2ImageMetadata, 168	•
enablePacketResend	isColorCamera, 138
fc2GigEConfig, 158	macAddress, 138
enabled	maximumBusSpeed, 138
fc2LUTData, 173	modelName, 138
exposure	nodeNumber, 138
fc2EmbeddedImageInfo, 149	pcieBusSpeed, 139
fo2AV/IOntion 122	reserved, 139
fc2AVIOption, 133	sensorInfo, 139
frameRate, 133	sensorResolution, 139
reserved, 133	serialNumber, 139
fc2AsyncCommandCallback	subnetMask, 139
Image saving structures., 126	userDefinedName, 139
fc2BMPOption, 134	vendorName, 139
indexedColor_8bit, 134	xmlURL1, 139
reserved, 134	xmlURL2, 139
fc2BandwidthAllocation	fc2CameraStats, 140
Enumerations, 109	cameraCurrents, 141
fc2BayerTileFormat	cameraPowerUp, 141
Enumerations, 110	cameraVoltages, 141
fc2BusCallbackType	imageCorrupt, 141
Enumerations, 110	imageDriverDropped, 141
fc2BusEventCallback	imageDropped, 141
Image saving structures., 126	imageXmitFailed, 141
fc2BusSpeed	numCurrents, 141
Enumerations, 110	numResendPacketsReceived, 141
fc2ByteOrder	numResendPacketsRequested, 141
FlyCapture2Defs_C.h, 216	numVoltages, 141
fc2CalculateImageStatistics	portErrors, 141
Image Operation, 78	regReadFailed, 142
fc2CallbackHandle	regWriteFailed, 142
Image saving structures., 126	reserved, 142
fc2CameraEventCallback	temperature, 142
Image saving structures., 126	timeSinceBusReset, 142

timeSinceInitialization, 142	fc2CreateTopologyNode
timeStamp, 142	TopologyNode Operation, 95
fc2CheckDriver	fc2DeregisterAllEvents
Utilities, 101	FlyCapture2_C.h, 208
fc2ColorProcessingAlgorithm	fc2DeregisterEvent
Enumerations, 111	FlyCapture2_C.h, 208
fc2Config, 142	fc2DestroyContext
asyncBusSpeed, 143	FlyCapture2_C.h, 208
bandwidthAllocation, 143	fc2DestroyGUIContext
grabMode, 143	FlyCapture2GUI_C.h, 218
grabTimeout, 143	fc2DestroyImage
highPerformanceRetrieveBuffer, 143	Image Operation, 80
isochBusSpeed, 144	fc2DestroyImageStatistics
minNumImageNotifications, 144	Image Statistics Operation, 87
numBuffers, 144	fc2DestroyTopologyNode
numImageNotifications, 144	TopologyNode Operation, 95
registerTimeout, 144	fc2DetermineBitsPerPixel
registerTimeoutRetries, 145	Image Operation, 80
reserved, 145	fc2Disconnect
fc2ConfigROM, 145	Connection and Image Retrieval, 25
chipldHi, 146	fc2DiscoverGigECameras
chipldLo, 146	Bus Manager Operation, 15
nodeVendorld, 146	fc2DiscoverGigEPacketSize
pszKeyword, 146	GigE property manipulation, 67
reserved, 146	fc2Disonnect
unitSWVer, 146	FlyCapture2GUI_C.h, 219
unitSpecId, 146	fc2DriverType
unitSubSWVer, 146	Enumerations, 112
vendorUniqueInfo_0, 147	fc2EmbeddedImageInfo, 147
vendorUniqueInfo_1, 147	GPIOPinState, 149
vendorUniqueInfo_2, 147	ROIPosition, 149
vendorUniqueInfo_3, 147	brightness, 149
fc2Connect	exposure, 149
Connection and Image Retrieval, 25	frameCounter, 149
fc2Context	gain, 149
TypeDefs, 105	shutter, 149
fc2ConvertImage	strobePattern, 149
Image Operation, 79	timestamp, 149
fc2ConvertImageTo	whiteBalance, 149
Image Operation, 79	fc2EmbeddedImageInfoProperty, 149
fc2CreateContext	available, 149
FlyCapture2_C.h, 207	onOff, 150
fc2CreateGUIContext	fc2EnableLUT
FlyCapture2GUI_C.h, 218	Look Up Table, 46
fc2CreateGigEContext	fc2Error
FlyCapture2_C.h, 207	Enumerations, 112
fc2CreateImage	fc2ErrorToDescription
Image Operation, 79	Utilities, 102
fc2CreateImageStatistics	fc2EventCallbackData, 150
Image Statistics Operation, 87	EventData, 150

EventDataSize, 150	unitBytesPerPacket, 157
EventID, 151	fc2FrameRate
EventName, 151	Enumerations, 114
EventTimestamp, 151	fc2GUIConnect
EventUserData, 151	FlyCapture2GUI_C.h, 219
EventUserDataSize, 151	fc2GUIDisconnect
fc2EventOptions, 151	FlyCapture2GUI_C.h, 219
EventCallbackFcn, 152	fc2GetActiveLUTBank
EventName, 152	Look Up Table, 47
EventUserData, 152	fc2GetCameraFromIPAddress
EventUserDataSize, 152	Bus Manager Operation, 17
fc2FireBusReset	fc2GetCameraFromIndex
Bus Manager Operation, 15	Bus Manager Operation, 17
fc2FireSoftwareTrigger	fc2GetCameraFromSerialNumber
Trigger, 38	Bus Manager Operation, 17
fc2FireSoftwareTriggerBroadcast	fc2GetCameraInfo
Trigger, 38	Information and Properties, 32
fc2ForceAllIPAddressesAutomatically	fc2GetCameraSerialNumberFromIndex
Bus Manager Operation, 16	Bus Manager Operation, 18
fc2ForceIPAddressAutomatically	fc2GetChannelHistogram
Bus Manager Operation, 16	Image Statistics Operation, 88
fc2ForceIPAddressToCamera	fc2GetChannelMean
Bus Manager Operation, 16	Image Statistics Operation, 88
fc2Format7ImageSettings, 152	fc2GetChannelNumPixelValues
height, 153	Image Statistics Operation, 88
mode, 153	fc2GetChannelPixelValueRange
offsetX, 153	Image Statistics Operation, 89
offsetY, 153	fc2GetChannelRange
pixelFormat, 153	Image Statistics Operation, 89
reserved, 153	fc2GetChannelStatus
width, 153	Image Statistics Operation, 90
fc2Format7Info, 154	fc2GetConfiguration
imageHStepSize, 155	Connection and Image Retrieval, 25
imageVStepSize, 155	fc2GetCycleTime
maxHeight, 155	FlyCapture2_C.h, 209
maxPacketSize, 155	fc2GetDefaultColorProcessing
maxWidth, 155	Image Operation, 80
minPacketSize, 155	fc2GetDefaultOutputFormat
mode, 155	Image Operation, 81
offsetHStepSize, 155	fc2GetDeviceFromIndex
offsetVStepSize, 155	Bus Manager Operation, 18
packetSize, 155	fc2GetDriverDeviceName
percentage, 156	Utilities, 102
pixelFormatBitField, 156	fc2GetEmbeddedImageInfo
reserved, 156	Memory Channels, 50
vendorPixelFormatBitField, 156	fc2GetFormat7Configuration
fc2Format7PacketInfo, 156	Format7, 60
maxBytesPerPacket, 157	fc2GetFormat7Info
recommendedBytesPerPacket, 157	Format7, 61
reserved, 157	fc2GetGPIOPinDirection

General Purpose Input / Output, 35	Information and Properties, 33
fc2GetGigEConfig	fc2GetRegisterString
GigE image stream configuration, 74	Register Operation, 54
fc2GetGigEImageBinningSettings	fc2GetStats
GigE image binning settings, 72	FlyCapture2 C.h, 209
fc2GetGigEImageSettings	fc2GetStrobe
GigE image settings, 69	Strobe, 43
fc2GetGigEImageSettingsInfo	fc2GetStrobeInfo
GigE image settings, 70	Strobe, 44
fc2GetGigEImagingMode	fc2GetSystemInfo
GigE image settings, 70	Utilities, 102
fc2GetGigEProperty	fc2GetTopology
GigE property manipulation, 67	Bus Manager Operation, 20
fc2GetGigEStreamChannelInfo	fc2GetTriggerDelay
GigE image stream configuration, 75	Trigger, 38
fc2GetImageColorProcessing	fc2GetTriggerDelayInfo
Image Operation, 81	Trigger, 39
fc2GetImageData	fc2GetTriggerMode
Image Operation, 81	Trigger, 39
fc2GetImageDimensions	
	fc2GetTriggerModeInfo
Image Operation, 82 fc2GetImageMetadata	Trigger, 40 fc2GetUsbLinkInfo
•	
Image Operation, 82	Bus Manager Operation, 20
fc2GetImageStatistics	fc2GetUsbPortStatus
Image Statistics Operation, 90	Bus Manager Operation, 20
fc2GetImageTimeStamp	fc2GetVideoModeAndFrameRate
Image Operation, 82	DCAM Formats, 58
fc2GetInterfaceTypeFromGuid	fc2GetVideoModeAndFrameRateInfo
Bus Manager Operation, 18	DCAM Formats, 59
fc2GetLUTBankInfo	fc2GigEConfig, 157
Look Up Table, 47	enablePacketResend, 158
fc2GetLUTChannel	registerTimeout, 158
Look Up Table, 47	registerTimeoutRetries, 158
fc2GetLUTInfo	reserved, 158
Look Up Table, 48	fc2GigEImageSettings, 158
fc2GetLibraryVersion	height, 159
Utilities, 102	offsetX, 159
fc2GetMemoryChannel	offsetY, 159
Memory Channels, 51	pixelFormat, 159
fc2GetMemoryChannelInfo	reserved, 159
Memory Channels, 51	width, 159
fc2GetNumOfCameras	fc2GigEImageSettingsInfo, 159
Bus Manager Operation, 19	imageHStepSize, 160
fc2GetNumOfDevices	imageVStepSize, 160
Bus Manager Operation, 19	maxHeight, 160
fc2GetNumStreamChannels	maxWidth, 160
GigE image stream configuration, 75	offsetHStepSize, 160
fc2GetProperty	offsetVStepSize, 160
Information and Properties, 32	pixelFormatBitField, 161
fc2GetPropertyInfo	reserved, 161

vendorPixelFormatBitField, 161	fc2ImageImpl
fc2GigEProperty, 161	TypeDefs, 106
isReadable, 162	fc2ImageMetadata, 166
isWritable, 162	embeddedBrightness, 167
max, 162	embeddedExposure, 167
min, 162	embeddedFrameCounter, 167
propType, 162	embeddedGPIOPinState, 167
reserved, 162	embeddedGain, 167
value, 162	embeddedROIPosition, 167
fc2GigEPropertyType	embeddedShutter, 168
GigE specific enumerations, 120	embeddedStrobePattern, 168
fc2GigEStreamChannel, 162	embeddedTimeStamp, 168
destinationlpAddress, 163	embeddedWhiteBalance, 168
doNotFragment, 164	reserved, 168
hostPort, 164	fc2ImageStatisticsContext
interPacketDelay, 164	TypeDefs, 106
networkInterfaceIndex, 164	fc2ImageStatisticsDisableAll
packetSize, 164	Image Statistics Operation, 91
reserved, 164	fc2ImageStatisticsEnableAll
sourcePort, 164	Image Statistics Operation, 91
fc2GrabMode	fc2ImageStatisticsEnableGreyOnly
Enumerations, 114	Image Statistics Operation, 92
fc2GrabTimeout	fc2ImageStatisticsEnableHSLOnly
Enumerations, 115	Image Statistics Operation, 92
fc2GuiContext	fc2ImageStatisticsEnableRGBOnly
TypeDefs, 106	Image Statistics Operation, 92
fc2H264Option, 164	fc2InterfaceType
bitrate, 165	Enumerations, 115
frameRate, 165	fc2InternalContext, 168
height, 165	pBusMgr, 168
reserved, 165	pCamera, 168
width, 165	fc2InternalGuiContext, 169
fc2Hide	pCameraControlDlg, 169
FlyCapture2GUI_C.h, 220	pCameraSelectionDlg, 169
fc2IPAddress, 170	fc2InternalImageCallback, 169
octets, 170	pCallback, 169
fc2Image, 165	pCallbackData, 170
bayerFormat, 166	fc2lsCameraControlable
cols, 166	Bus Manager Operation, 21
dataSize, 166	fc2IsConnected
format, 166	Connection and Image Retrieval, 26
imageImpl, 166	fc2lsVisible
pData, 166	FlyCapture2GUI_C.h, 220
receivedDataSize, 166	fc2JPEGOption, 170
rows, 166	progressive, 171
stride, 166	quality, 171
fc2ImageEventCallback	reserved, 171
Image saving structures., 126	fc2JPG2Option, 171
fc2ImageFileFormat	quality, 172
Enumerations, 115	reserved, 172
, -	•

fc2LUTData, 172	GigE image settings, 70
enabled, 173	fc2ReadGVCPMemory
inputBitDepth, 173	GVCP Register Operation, 63
numBanks, 173	fc2ReadGVCPRegister
numChannels, 173	GVCP Register Operation, 64
numEntries, 173	fc2ReadGVCPRegisterBlock
outputBitDepth, 173	GVCP Register Operation, 64
reserved, 173	fc2ReadPhyRegister
supported, 173	Bus Manager Operation, 21
fc2LaunchBrowser	fc2ReadRegister
Utilities, 103	Register Operation, 54
fc2LaunchCommand	fc2ReadRegisterBlock
Utilities, 103	Register Operation, 55
fc2LaunchCommandAsync	fc2RegisterAllEvents
Utilities, 103	FlyCapture2_C.h, 209
fc2LaunchHelp	fc2RegisterCallback
Utilities, 104	Bus Manager Operation, 21
fc2MACAddress, 173	fc2RegisterEvent
octets, 174	FlyCapture2_C.h, 210
fc2MJPGOption, 174	fc2RescanBus
frameRate, 174	Bus Manager Operation, 22
quality, 174	fc2RestoreFromMemoryChannel
reserved, 174	Memory Channels, 51
fc2Mode	fc2RetrieveBuffer
Enumerations, 116	Connection and Image Retrieval, 26
fc2NodeType	fc2SaveImage
FlyCapture2Defs_C.h, 216	Image Operation, 83
fc2OSType	fc2SaveImageWithOption
FlyCapture2Defs_C.h, 217	Image Operation, 83
fc2PCleBusSpeed	fc2SaveToMemoryChannel
Enumerations, 117	Memory Channels, 52
fc2PGMOption, 175	fc2SetActiveLUTBank
binaryFile, 175	Look Up Table, 48
reserved, 175	fc2SetCallback
fc2PGRGuid, 175	Connection and Image Retrieval, 27
value, 176	fc2SetChannelStatus
fc2PNGOption, 176	Image Statistics Operation, 93
compressionLevel, 176	fc2SetConfiguration
interlaced, 176	Connection and Image Retrieval, 27
reserved, 176	fc2SetDefaultColorProcessing
fc2PPMOption, 177	Image Operation, 83
binaryFile, 177	fc2SetDefaultOutputFormat
reserved, 177	Image Operation, 84
fc2PixelFormat	fc2SetEmbeddedImageInfo
Enumerations, 117	Memory Channels, 52
fc2PortType	fc2SetFormat7Configuration
FlyCapture2Defs_C.h, 217	Format7, 61
fc2PropertyType	fc2SetFormat7ConfigurationPacket
Enumerations, 118	Format7, 61
fc2QueryGigEImagingMode	fc2SetGPIOPinDirection

General Purpose Input / Output, 35	Connection and Image Retrieval, 29
fc2SetGPIOPinDirectionBroadcast	fc2StartSyncCapture
General Purpose Input / Output, 36	Connection and Image Retrieval, 29
fc2SetGigEConfig	fc2StartSyncCaptureCallback
GigE image stream configuration, 75	Connection and Image Retrieval, 30
fc2SetGigEImageBinningSettings	fc2StatisticsChannel
GigE image binning settings, 72	FlyCapture2Defs_C.h, 217
fc2SetGigEImageSettings	fc2StopCapture
GigE image settings, 70	Connection and Image Retrieval, 30
fc2SetGigEImagingMode	fc2StrobeControl, 177
GigE image settings, 71	delay, 178
fc2SetGigEProperty	duration, 178
GigE property manipulation, 68	onOff, 178
fc2SetGigEStreamChannelInfo	polarity, 178
GigE image stream configuration, 76	reserved, 178
fc2SetImageColorProcessing	source, 178
Image Operation, 84	fc2Strobelnfo, 179
fc2SetImageData	maxValue, 179
Image Operation, 84	minValue, 179
fc2SetImageDimensions	onOffSupported, 180
Image Operation, 85	polaritySupported, 180
fc2SetLUTChannel	present, 180
Look Up Table, 49	readOutSupported, 180
fc2SetProperty	reserved, 180
Information and Properties, 34	source, 180
fc2SetPropertyBroadcast	fc2SystemInfo, 180
Information and Properties, 34	byteOrder, 181
fc2SetStrobe	cpuDescription, 181
Strobe, 44	driverList, 181
fc2SetStrobeBroadcast	gpuDescription, 181
Strobe, 44	libraryList, 181
fc2SetTriggerDelay	numCpuCores, 182
Trigger, 40	osDescription, 182
fc2SetTriggerDelayBroadcast	osType, 182
Trigger, 41	reserved, 182
fc2SetTriggerMode	screenHeight, 182
Trigger, 41	screenWidth, 182
fc2SetTriggerModeBroadcast	sysMemSize, 182
Trigger, 42	fc2TIFFCompressionMethod
fc2SetUserBuffers	Image saving structures., 126
Connection and Image Retrieval, 28	fc2TIFFOption, 182
fc2SetVideoModeAndFrameRate	compression, 183
DCAM Formats, 59	reserved, 183
fc2Show	fc2TimeStamp, 183
FlyCapture2GUI_C.h, 220	cycleCount, 184
fc2ShowModal	cycleOffset, 184
FlyCapture2GUI_C.h, 220	cycleSeconds, 184
fc2StartCapture	microSeconds, 184
Connection and Image Retrieval, 28	reserved, 184
fc2StartCaptureCallback	seconds, 184

fc2TopologyNodeAddChild	readOutSupported, 189
TopologyNode Operation, 96	reserved, 189
fc2TopologyNodeAddPortType	type, 189
TopologyNode Operation, 96	fc2TriggerMode, 189
fc2TopologyNodeAssignGuidToNode	mode, 190
TopologyNode Operation, 96	onOff, 190
fc2TopologyNodeAssignGuidToNodeEx	parameter, 190
TopologyNode Operation, 97	polarity, 190
fc2TopologyNodeContext	reserved, 190
TypeDefs, 106	source, 190
fc2TopologyNodeGetChild	fc2TriggerModeInfo, 190
TopologyNode Operation, 97	modeMask, 191
fc2TopologyNodeGetDeviceId	onOffSupported, 191
TopologyNode Operation, 98	polaritySupported, 191
fc2TopologyNodeGetGuid	present, 191
TopologyNode Operation, 98	readOutSupported, 191
fc2TopologyNodeGetInterfaceType	reserved, 191
TopologyNode Operation, 98	softwareTriggerSupported, 192
fc2TopologyNodeGetNodeType	sourceMask, 192
TopologyNode Operation, 99	valueReadable, 192
fc2TopologyNodeGetNumChildren	fc2UnregisterCallback
TopologyNode Operation, 99	Bus Manager Operation, 22
fc2TopologyNodeGetNumPorts	fc2ValidateFormat7Settings
TopologyNode Operation, 100	Format7, 62
fc2TopologyNodeGetPortType	fc2Version, 192
TopologyNode Operation, 100	build, 193
fc2TriggerDelay, 184	major, 193
absControl, 185	minor, 193
absValue, 185	type, 193
autoManualMode, 186	fc2VideoAVIOpen
onOff, 186	Video Recording Operation, 128
onePush, 186	fc2VideoAppend
present, 186	Video Recording Operation, 127
reserved, 186	fc2VideoClose
type, 186	Video Recording Operation, 128
valueA, 186	fc2VideoContext
valueB, 186	TypeDefs, 106
fc2TriggerDelayInfo, 187	fc2VideoCreate
absMax, 188	Video Recording Operation, 128
absMin, 188	fc2VideoDestroy
absValSupported, 188	Video Recording Operation, 129
autoSupported, 188	fc2VideoH264Open
manualSupported, 188	Video Recording Operation, 129
max, 188	fc2VideoMJPGOpen
min, 188	Video Recording Operation, 130
onOffSupported, 188	fc2VideoMode
onePushSupported, 188	Enumerations, 118
pUnitAbbr, 188	fc2VideoSetMaximumSize
pUnits, 189	Video Recording Operation, 130
present, 188	fc2WaitForBufferEvent

Connection and Image Retrieval, 31 fc2WriteGVCPMemory	fc2GigEStreamChannel, 164
GVCP Register Operation, 64	iidcVer
fc2WriteGVCPRegister	fc2CameraInfo, 138
GVCP Register Operation, 65	imageCorrupt
fc2WriteGVCPRegisterBlock	fc2CameraStats, 141
GVCP Register Operation, 65	imageDriverDropped
fc2WriteGVCPRegisterBroadcast	fc2CameraStats, 141
GVCP Register Operation, 65	imageDropped
fc2WritePhyRegister	fc2CameraStats, 141
, ,	imageHStepSize
Bus Manager Operation, 22	fc2Format7Info, 155
fc2WriteRegister	fc2GigEImageSettingsInfo, 160
Register Operation, 55	
fc2WriteRegisterBlock	imageImpl
Register Operation, 56	fc2Image, 166
fc2WriteRegisterBroadcast	imageVStepSize
Register Operation, 56	fc2Format7Info, 155
firmwareBuildTime	fc2GigEImageSettingsInfo, 160
fc2CameraInfo, 137	imageXmitFailed
firmwareVersion	fc2CameraStats, 141
fc2CameraInfo, 137	indexedColor_8bit
format	fc2BMPOption, 134
fc2Image, 166	inputBitDepth
frameCounter	fc2LUTData, 173
fc2EmbeddedImageInfo, 149	interPacketDelay
frameRate	fc2GigEStreamChannel, 164
fc2AVIOption, 133	interfaceType
fc2H264Option, 165	fc2CameraInfo, 138
fc2MJPGOption, 174	interlaced
	fc2PNGOption, 176
gain	ipAddress
fc2EmbeddedImageInfo, 149	fc2CameraInfo, 138
gigEMajorVersion	isColorCamera
fc2CameraInfo, 138	fc2CameraInfo, 138
gigEMinorVersion	isReadable
fc2CameraInfo, 138	fc2GigEProperty, 162
gpuDescription	isWritable
fc2SystemInfo, 181	fc2GigEProperty, 162
grabMode	isochBusSpeed
fc2Config, 143	fc2Config, 144
grabTimeout	
fc2Config, 143	libraryList
	fc2SystemInfo, 181
height	
fc2Format7ImageSettings, 153	macAddress
fc2GigEImageSettings, 159	fc2CameraInfo, 138
fc2H264Option, 165	major
highPerformanceRetrieveBuffer	fc2Version, 193
fc2Config, 143	manualSupported
hostPort	fc2TriggerDelayInfo, 188

	fa0LLITData 170
max	fc2LUTData, 173
fc2GigEProperty, 162	numCpuCores
fc2TriggerDelayInfo, 188	fc2SystemInfo, 182
maxBytesPerPacket	numCurrents
fc2Format7PacketInfo, 157	fc2CameraStats, 141
maxHeight	numEntries
fc2Format7Info, 155	fc2LUTData, 173
fc2GigEImageSettingsInfo, 160	numImageNotifications
maxPacketSize	fc2Config, 144
fc2Format7Info, 155	numResendPacketsReceived
maxValue	fc2CameraStats, 141
fc2StrobeInfo, 179	numResendPacketsRequested
maxWidth	fc2CameraStats, 141
fc2Format7Info, 155	numVoltages
fc2GigEImageSettingsInfo, 160	fc2CameraStats, 141
maximumBusSpeed	
fc2CameraInfo, 138	octets
microSeconds	fc2IPAddress, 170
fc2TimeStamp, 184	fc2MACAddress, 174
min	offsetHStepSize
fc2GigEProperty, 162	fc2Format7Info, 155
fc2TriggerDelayInfo, 188	fc2GigEImageSettingsInfo, 160
minNumImageNotifications	offsetVStepSize
fc2Config, 144	fc2Format7Info, 155
minPacketSize	fc2GigEImageSettingsInfo, 160
fc2Format7Info, 155	offsetX
minValue	fc2Format7ImageSettings, 153
fc2Strobelnfo, 179	fc2GigEImageSettings, 159
minor	offsetY
fc2Version, 193	fc2Format7ImageSettings, 153
mode	fc2GigEImageSettings, 159
fc2Format7ImageSettings, 153	onOff
ICZFORMAL/INIO, 155	fc2EmbeddedImageInfoProperty,
fc2Format7Info, 155 fc2TriggerMode, 190	fc2EmbeddedImageInfoProperty, 150
fc2TriggerMode, 190	150
fc2TriggerMode, 190 modeMask	150 fc2StrobeControl, 178
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191	150 fc2StrobeControl, 178 fc2TriggerDelay, 186
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName	150 fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191	150 fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138 networkInterfaceIndex	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138 networkInterfaceIndex fc2GigEStreamChannel, 164	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191 onePush
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191 onePush fc2TriggerDelay, 186
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138 nodeVendorId	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191 onePush fc2TriggerDelay, 186 onePushSupported
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138 nodeVendorId fc2ConfigROM, 146	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerDelayInfo, 191 onePush fc2TriggerDelay, 186 onePushSupported fc2TriggerDelayInfo, 188
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138 nodeVendorId fc2ConfigROM, 146 numBanks	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191 onePush fc2TriggerDelay, 186 onePushSupported fc2TriggerDelayInfo, 188 osDescription
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138 nodeVendorId fc2ConfigROM, 146 numBanks fc2LUTData, 173	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191 onePush fc2TriggerDelay, 186 onePushSupported fc2TriggerDelayInfo, 188 osDescription fc2SystemInfo, 182
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138 nodeVendorId fc2ConfigROM, 146 numBanks fc2LUTData, 173 numBuffers	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerDelayInfo, 191 onePush fc2TriggerDelay, 186 onePushSupported fc2TriggerDelayInfo, 188 osDescription fc2SystemInfo, 182 osType
fc2TriggerMode, 190 modeMask fc2TriggerModeInfo, 191 modelName fc2CameraInfo, 138  networkInterfaceIndex fc2GigEStreamChannel, 164 nodeNumber fc2CameraInfo, 138 nodeVendorId fc2ConfigROM, 146 numBanks fc2LUTData, 173	fc2StrobeControl, 178 fc2TriggerDelay, 186 fc2TriggerMode, 190 onOffSupported fc2StrobeInfo, 180 fc2TriggerDelayInfo, 188 fc2TriggerModeInfo, 191 onePush fc2TriggerDelay, 186 onePushSupported fc2TriggerDelayInfo, 188 osDescription fc2SystemInfo, 182

fc2LUTData, 173	propType fc2GigEProperty, 162
pBusMgr	pszKeyword
fc2InternalContext, 168	fc2ConfigROM, 146
pCallback	3 - , -
fc2InternalImageCallback, 169	quality
pCallbackData	fc2JPEGOption, 171
fc2InternalImageCallback, 170	fc2JPG2Option, 172
pCamera	fc2MJPGOption, 174
fc2InternalContext, 168	
pCameraControlDlg	readOutSupported
fc2InternalGuiContext, 169	fc2StrobeInfo, 180
pCameraSelectionDlg	fc2TriggerDelayInfo, 189
fc2InternalGuiContext, 169	fc2TriggerModeInfo, 191
pData	receivedDataSize
fc2Image, 166	fc2Image, 166
pUnitAbbr	recommendedBytesPerPacket
fc2TriggerDelayInfo, 188	fc2Format7PacketInfo, 157
pUnits	regReadFailed
fc2TriggerDelayInfo, 189	fc2CameraStats, 142
packetSize	regWriteFailed
fc2Format7Info, 155	fc2CameraStats, 142
fc2GigEStreamChannel, 164	registerTimeout
parameter	fc2Config, 144
fc2TriggerMode, 190	fc2GigEConfig, 158
pcieBusSpeed	registerTimeoutRetries
fc2CameraInfo, 139	fc2Config, 145
percentage	fc2GigEConfig, 158
fc2Format7Info, 156	reserved
pixelFormat	fc2AVIOption, 133
fc2Format7ImageSettings, 153	fc2BMPOption, 134
fc2GigEImageSettings, 159	fc2CameraInfo, 139
pixelFormatBitField	fc2CameraStats, 142
fc2Format7Info, 156	fc2Config, 145
fc2GigEImageSettingsInfo, 161	fc2ConfigROM, 146
polarity	fc2Format7ImageSettings, 153
fc2StrobeControl, 178	fc2Format7Info, 156
fc2TriggerMode, 190	fc2Format7PacketInfo, 157
polaritySupported	fc2GigEConfig, 158
fc2StrobeInfo, 180	fc2GigEImageSettings, 159
fc2TriggerModeInfo, 191	fc2GigEImageSettingsInfo, 161
portErrors	fc2GigEProperty, 162
fc2CameraStats, 141	fc2GigEStreamChannel, 164
present	fc2H264Option, 165
fc2Strobelnfo, 180	fc2lmageMetadata, 168
fc2TriggerDelay, 186	fc2JPEGOption, 171
fc2TriggerDelayInfo, 188	fc2JPG2Option, 172
fc2TriggerModeInfo, 191	fc2LUTData, 173
progressive	fc2MJPGOption, 174
fc2JPEGOption, 171	fc2PGMOption, 175

	_
fc2PNGOption, 176	syncDestroyContext
fc2PPMOption, 177	MultiSyncLibrary_C.h, 224
fc2StrobeControl, 178	syncDisableCrossPCSynchronization
fc2StrobeInfo, 180	MultiSyncLibrary_C.h, 225
fc2SystemInfo, 182	syncEnableCrossPCSynchronization
fc2TIFFOption, 183	MultiSyncLibrary_C.h, 225
fc2TimeStamp, 184	syncError
fc2TriggerDelay, 186	MultiSyncLibraryDefs_C.h, 229
fc2TriggerDelayInfo, 189	syncGetStatus
fc2TriggerMode, 190	MultiSyncLibrary_C.h, 225
fc2TriggerModeInfo, 191	syncGetTimeSinceSynced
rows	MultiSyncLibrary_C.h, 226
fc2lmage, 166	syncIsTimingBusConnected
	MultiSyncLibrary_C.h, 226
screenHeight	syncMessage
fc2SystemInfo, 182	MultiSyncLibraryDefs_C.h, 229
screenWidth	syncQueryCrossPCSynchronization-
fc2SystemInfo, 182	Setting
seconds	MultiSyncLibrary_C.h, 226
fc2TimeStamp, 184	syncRescanMasterTimingBus
sensorInfo	MultiSyncLibrary_C.h, 227
fc2CameraInfo, 139	syncStart
sensorResolution	MultiSyncLibrary_C.h, 227
fc2CameraInfo, 139	syncStop
serialNumber	MultiSyncLibrary_C.h, 227
fc2CameraInfo, 139	sysMemSize
shutter	fc2SystemInfo, 182
fc2EmbeddedImageInfo, 149	1620ysterrinio, 162
softwareTriggerSupported	temperature
fc2TriggerModeInfo, 192	fc2CameraStats, 142
source	timeSinceBusReset
fc2StrobeControl, 178	fc2CameraStats, 142
fc2StrobeInfo, 180	timeSinceInitialization
fc2TriggerMode, 190	fc2CameraStats, 142
sourceMask	timeStamp
fc2TriggerModeInfo, 192	fc2CameraStats, 142
sourcePort	timestamp
fc2GigEStreamChannel, 164	•
stride	fc2EmbeddedImageInfo, 149
fc2Image, 166	type
strobePattern	fc2TriggerDelay, 186
	fc2TriggerDelayInfo, 189
fc2EmbeddedImageInfo, 149	fc2Version, 193
subnetMask	unitBytesPerPacket
fc2CameraInfo, 139	
supported	fc2Format7PacketInfo, 157
fc2LUTData, 173	unitSWVer
syncContext	fc2ConfigROM, 146
MultiSyncLibraryDefs_C.h, 228	unitSpecId
syncCreateContext	fc2ConfigROM, 146
MultiSyncLibrary_C.h, 224	unitSubSWVer

```
fc2ConfigROM, 146
userDefinedName
    fc2CameraInfo, 139
value
    fc2GigEProperty, 162
    fc2PGRGuid, 176
valueA
    fc2TriggerDelay, 186
valueB
    fc2TriggerDelay, 186
valueReadable
    fc2TriggerModeInfo, 192
vendorName
    fc2CameraInfo, 139
vendorPixelFormatBitField
    fc2Format7Info, 156
    fc2GigEImageSettingsInfo, 161
vendorUniqueInfo_0
    fc2ConfigROM, 147
vendorUniqueInfo_1
    fc2ConfigROM, 147
vendorUniqueInfo_2
    fc2ConfigROM, 147
vendorUniqueInfo_3
    fc2ConfigROM, 147
whiteBalance
    fc2EmbeddedImageInfo, 149
width
    fc2Format7ImageSettings, 153
    fc2GigEImageSettings, 159
    fc2H264Option, 165
xmlURL1
    fc2CameraInfo, 139
xmIURL2
    fc2CameraInfo, 139
```